

# ls1x0ls1x0cs100a.dll

LS-1x0 & CS-100A Support **D**ynamic **L**ink **L**ibrary

Version 1.0.0000  
February 2003

© Copyright by Minolta Europe, U. Strahlendorf

## Table of contents

Table of contents .....	2
Introduction .....	4
System requirements .....	4
Installation .....	4
RS-232C communication port .....	5
Connection of LS-1x0 & CS-100a and PC .....	5
Setting LS-1x0 or CS-100A into two-directional communication mode .....	5
DLL functions related to communication .....	5
OpenComm .....	6
CloseComm .....	7
CS-100a support functions .....	8
cs100aCLE .....	9
cs100aMDS .....	10
cs100aMES .....	11
cs100aRCR .....	12
cs100aTDR .....	13
cs100aTDS .....	14
cs100aTDW .....	15
cs100aUCR .....	16
cs100aUCW .....	17
LS-1x0 support functions .....	18
Ls100CLE .....	19
Ls100MDS .....	20
ls100MES .....	21
ls100DSR .....	22
ls100CMR .....	23
ls100CMS .....	24
ls100CMW .....	25
ls100LMR .....	26
ls100LMW .....	27
ls100CCR .....	28
ls100CCW .....	29
Colorimetric support functions .....	30
YxyToXYZ .....	31
xyToDomWL .....	32
xyTouv .....	33
xyToudvd .....	34
xyToRGBLong .....	35
XYZTouv .....	36
XYZToudvd .....	37
XYZToRGBLong .....	38
uvToTduv .....	39
RGBLongToRGB .....	40
Include modules” for VBA & VB .....	41
VBA Visual Basic for Applications .....	41
VB Visual Basic .....	41
CS-100A Examples by using Microsoft EXCEL .....	42
Yxy measurement and graphical display .....	42
Yxy measurement and uv (u'v') graphical display .....	43
Yxy multi measurement and graphical display .....	44
Sequence measurement .....	45

Sequence of difference measurements .....	46
Tools.....	47
LS-1x0 Examples by using Microsoft EXCEL.....	49
Sequence measurement and graphical display .....	49
Sequence of difference measurements .....	50
Tools.....	51
CCF definition.....	53
Appendix .....	54
Colorimetric calculations: .....	54
1931 CIE Chromaticity System (Yxy) .....	54
1960 CIE Uniform Color Space System (uv).....	54
1976 CIE Uniform Color Space System (u'v') .....	54

## Introduction

This DLL is made to simplify communication with the Minolta Luminance Meter LS-100, LS-110 and Minolta Chroma Meter CS-100A. In addition it provides multiple colorimetric calculation functions.

All commands available by LS-1x0 and CS-100A are supported. By using program language like Visual Basic (for application) or others, full control of LS-1x0 and CS-100A is possible.

An Example by using Microsoft EXCEL is included as well as this full documentation of the DLL and the EXCEL example.

## System requirements

IBM compatible PC

Operation system: Windows 95, Windows 98, Windows ME, Windows NT 4.0, Windows 2000, Windows XP

Programming:

Windows 32 Bit compatible programming language like Visual Basic 4.0 or higher, Visual C++ or others.

For Excel sample file:

Microsoft EXCEL 97 or newer

Recommended screen resolution: 1024 \* 768 or higher (true color)

## Installation

As this is just a DLL and not a complete application, it doesn't come with a setup program. You only need to copy the "ls1x0ls1x0cs100a.dll" file to the proper location.

Depending on the way of usage there are two different locations:

If you are using the DLL from EXCEL or other Office application, please copy the file to the "Windows\System" folder.

If you are writing own software, best is to copy the DLL to the same folder like the EXE file of your application. This is the first place where Windows is searching for DLL files. Of course the "Windows\System" folder also would be OK.

### Note!

The remaining files like the EXCEL example and this manual don't require a specific location!

## **RS-232C communication port**

This section will explain about the usage of RS-232C port for connection to LS-1x0 and CS-100a.

### ***Connection of LS-1x0 & CS-100a and PC***

Minolta supplies different connection cables for the LS-1x0 and the CS-100a:

- LS-A12 RS connection cable CS-100A or LS-1x0 to PC (9 pin)
- LS-A15 RS connecting cable CS-100A or LS-1x0 to PC (9 pin) including AC-adaptor for power supply. AC-adaptor is connected to 9 pin connector at PC side, thus only one cable is going from PC to LS-1x0 or CS-100A

For details about connection please refer to LS-1x0 or CS-100A communication manual!

### ***Setting LS-1x0 or CS-100A into two-directional communication mode***

Check that LS-1x0 or CS-100A power is switched off

Switch power of LS-1x0 or CS-100A on while pressing the F key

The letter "C" will be displayed in the right bottom of LS-1x0 or CS-100A external display

#### **Notes!**

- **In two-directional communication mode no other keys or switches than the power switch are accepted by either LS-1x0 or CS-100A!**
- **In two-directional communication mode the power consumption of LS-1x0 or CS-100A is higher than in normal mode. It's recommended to use LS-A15 connection cable with external power supply.**

### ***DLL functions related to communication***

The ls1x0ls1x0cs100a.dll supports the communication ports 1 to 8! Thus you also should not face any problem by using USB to RS232C converter. The ls1x0ls1x0cs100a.dll has two functions for opening and closing a communication port.

#### **Note!**

**This program has not been tested with all the different USB converters. We cannot assure that this program is working properly with each single converter because this might be depending on the driver of the converter.**

<b>Function name:</b>		<b>Library:</b>															
<b>OpenComm</b>		ls1x0cs100a.dll															
<b>Function:</b> Open RS232C communication port																	
<b>Declaration: Visual Basic for Application – Ex: EXCEL (no Enum)</b> Public Declare Function OpenComm Lib "ls1x0ls1x0cs100a.dll" (ByVal fNum As Integer, ByVal PortNumber As Integer) As Long																	
<b>Declaration: Visual Basic (with Enum)</b> Public Declare Function OpenComm Lib "ls1x0ls1x0cs100a.dll" (ByVal fNum As Integer, ByVal PortNumber As cs100aComPort) As Long																	
<b>Parameter:</b>																	
<table><tr><th>Pass by:</th><th>Name:</th><th>Data type:</th><th>Data range:</th></tr><tr><td>ByVal</td><td>fNum</td><td>Integer</td><td></td></tr><tr><td>ByVal</td><td>PortNumber</td><td>Integer</td><td>1 – 8</td></tr></table>	Pass by:	Name:	Data type:	Data range:	ByVal	fNum	Integer		ByVal	PortNumber	Integer	1 – 8					
Pass by:	Name:	Data type:	Data range:														
ByVal	fNum	Integer															
ByVal	PortNumber	Integer	1 – 8														
<b>Parameter usage:</b>																	
<table><tr><th>Parameter:</th><th>Usage:</th></tr><tr><td>fNum</td><td>Specify a file number to be used for communication to this port. File number is typically requested by the FreeFile function</td></tr><tr><td rowspan="8">PortNumber</td><td>Specify a port number within a range of 1 to 8. This value is depending on the communication port to which your instrument is connected.</td></tr><tr><td><b>Predefined values in cs100a_VBdeclares.bas:</b> <b>(cs100aComPort Enumeration)</b></td></tr><tr><td>CsCOM1 = 1</td></tr><tr><td>CsCOM2 = 2</td></tr><tr><td>CsCOM3 = 3</td></tr><tr><td>CsCOM4 = 4</td></tr><tr><td>CsCOM5 = 5</td></tr><tr><td>CsCOM6 = 6</td></tr><tr><td>CsCOM7 = 7</td></tr><tr><td>CsCOM8 = 8</td></tr></table>	Parameter:	Usage:	fNum	Specify a file number to be used for communication to this port. File number is typically requested by the FreeFile function	PortNumber	Specify a port number within a range of 1 to 8. This value is depending on the communication port to which your instrument is connected.	<b>Predefined values in cs100a_VBdeclares.bas:</b> <b>(cs100aComPort Enumeration)</b>	CsCOM1 = 1	CsCOM2 = 2	CsCOM3 = 3	CsCOM4 = 4	CsCOM5 = 5	CsCOM6 = 6	CsCOM7 = 7	CsCOM8 = 8		
Parameter:	Usage:																
fNum	Specify a file number to be used for communication to this port. File number is typically requested by the FreeFile function																
PortNumber	Specify a port number within a range of 1 to 8. This value is depending on the communication port to which your instrument is connected.																
	<b>Predefined values in cs100a_VBdeclares.bas:</b> <b>(cs100aComPort Enumeration)</b>																
	CsCOM1 = 1																
	CsCOM2 = 2																
	CsCOM3 = 3																
	CsCOM4 = 4																
	CsCOM5 = 5																
	CsCOM6 = 6																
CsCOM7 = 7																	
CsCOM8 = 8																	
<b>Return type and value:</b>																	
<table><tr><th>Data</th><th>Explanation</th></tr><tr><td>Long</td><td>Use for Error-Checking</td></tr><tr><td>0</td><td>No error</td></tr><tr><td>-100</td><td>Invalid number for communication port. Must be integer in the range of 1 - 8</td></tr><tr><td>-101</td><td>Port could not be opened. Please make sure that the specified port exists and is not used by any other device.</td></tr></table>	Data	Explanation	Long	Use for Error-Checking	0	No error	-100	Invalid number for communication port. Must be integer in the range of 1 - 8	-101	Port could not be opened. Please make sure that the specified port exists and is not used by any other device.							
Data	Explanation																
Long	Use for Error-Checking																
0	No error																
-100	Invalid number for communication port. Must be integer in the range of 1 - 8																
-101	Port could not be opened. Please make sure that the specified port exists and is not used by any other device.																
<b>Notes:</b>																	

<b>Function name:</b>		<b>Library:</b>	
<b>CloseComm</b>		ls1x0cs100a.dll	
<b>Function:</b> Close RS232C communication port			
<b>Declaration:</b> Public Declare Function CloseComm Lib "ls1x0ls1x0cs100a.dll" (ByVal fNum As Integer) As Long			
<b>Parameter:</b>			
<b>Pass by:</b>	<b>Name:</b>	<b>Data type:</b>	<b>Data range:</b>
ByVal	fNum	Integer	
<b>Parameter usage:</b>			
<b>Parameter:</b>	<b>Usage:</b>		
fNum	Specify a file number, which was used to open this communication port.		
<b>Return type and value:</b>			
<b>Data</b>	<b>Explanation</b>		
Long	Use for Error-Checking		
0	No error		
-102	Port could not be closed. Please make sure that the specified file number is correct.		
<b>Notes:</b>			

## CS-100a support functions

Please see the following list of commands available by CS-100A

Command	Function	Page
CLE	Clears the memory of CS-100A	
MDS	Mode setting like absolute or difference measurement, fast of slow measurement mode and user calibration	
MES	Taking measurement according to the settings defined by MDS command	
RCR	Re-calculate the data in memory according the settings made by MDS command	
TDR	Read target data, which is stored in CS-100A for difference measurements.	
TDS	Set the measured value into target memory of CS-100A	
TDW	Write target values into CS-100A memory	
UCR	Read the standard value for measuring user calibration standard which is memorized in CS-100A	
UCW	Write the standard value for measuring user calibration standard into CS-100A memory	



<b>Function name:</b>  <b>cs100aCLE</b>		<b>Library:</b> 1x0cs100a.dll																			
<b>Function:</b> Clears the memory of connected CS-100A																					
<b>Declaration:</b> Public Declare Function cs100aCLE Lib "ls1x0ls1x0cs100a.dll" (ByVal fNum As Integer) As Long																					
<b>Parameter:</b>																					
<table><tr><td><b>Pass by:</b></td><td><b>Name:</b></td><td><b>Data type:</b></td><td><b>Data range:</b></td></tr><tr><td>ByVal</td><td>fNum</td><td>Integer</td><td></td></tr></table>		<b>Pass by:</b>	<b>Name:</b>	<b>Data type:</b>	<b>Data range:</b>	ByVal	fNum	Integer													
<b>Pass by:</b>	<b>Name:</b>	<b>Data type:</b>	<b>Data range:</b>																		
ByVal	fNum	Integer																			
<b>Parameter usage:</b>																					
<table><tr><td><b>Parameter:</b></td><td><b>Usage:</b></td></tr><tr><td>fNum</td><td>Specify a file number, which was used to open this communication port.</td></tr></table>		<b>Parameter:</b>	<b>Usage:</b>	fNum	Specify a file number, which was used to open this communication port.																
<b>Parameter:</b>	<b>Usage:</b>																				
fNum	Specify a file number, which was used to open this communication port.																				
<b>Return type and value:</b>																					
<table><tr><td><b>Data</b></td><td><b>Explanation</b></td></tr><tr><td>Long</td><td>Use for Error-Checking</td></tr><tr><td>0</td><td>No error</td></tr><tr><td>-11</td><td>ER11: Memory value Error!</td></tr><tr><td>-20</td><td>ER20: EEPROM Error!</td></tr><tr><td>-30</td><td>ER30: Low battery!</td></tr><tr><td>-103</td><td>Timeout: CS-100A didn't answer in proper time!</td></tr><tr><td>-104</td><td>Communication error: Please check for correct file number</td></tr><tr><td>-105</td><td>Command error: Wrong command or parameter was sent to CS-100A</td></tr></table>		<b>Data</b>	<b>Explanation</b>	Long	Use for Error-Checking	0	No error	-11	ER11: Memory value Error!	-20	ER20: EEPROM Error!	-30	ER30: Low battery!	-103	Timeout: CS-100A didn't answer in proper time!	-104	Communication error: Please check for correct file number	-105	Command error: Wrong command or parameter was sent to CS-100A		
<b>Data</b>	<b>Explanation</b>																				
Long	Use for Error-Checking																				
0	No error																				
-11	ER11: Memory value Error!																				
-20	ER20: EEPROM Error!																				
-30	ER30: Low battery!																				
-103	Timeout: CS-100A didn't answer in proper time!																				
-104	Communication error: Please check for correct file number																				
-105	Command error: Wrong command or parameter was sent to CS-100A																				
<b>Notes:</b>																					

<b>Function name:</b>  <b>cs100aMDS</b>			<b>Library:</b> ls1x0cs100a.dll																				
<b>Function:</b> Mode setting																							
<b>Declaration: Visual Basic for Application – Ex: EXCEL (no Enum)</b> Public Declare Function cs100aMDS Lib "ls1x0ls1x0cs100a.dll" (ByVal fNum As Integer, ByVal Mode As Integer) As Long																							
<b>Declaration: Visual Basic (with Enum)</b> Public Declare Function cs100aMDS Lib "ls1x0ls1x0cs100a.dll" (ByVal fNum As Integer, ByVal Mode As cs100aMode) As Long																							
<b>Parameter:</b>																							
<table><tr><td><b>Pass by:</b></td><td><b>Name:</b></td><td><b>Data type:</b></td><td><b>Data range:</b></td></tr><tr><td>ByVal</td><td>fNum</td><td>Integer</td><td></td></tr><tr><td>ByVal</td><td>Mode</td><td>Integer</td><td>0,1,4-7</td></tr></table>				<b>Pass by:</b>	<b>Name:</b>	<b>Data type:</b>	<b>Data range:</b>	ByVal	fNum	Integer		ByVal	Mode	Integer	0,1,4-7								
<b>Pass by:</b>	<b>Name:</b>	<b>Data type:</b>	<b>Data range:</b>																				
ByVal	fNum	Integer																					
ByVal	Mode	Integer	0,1,4-7																				
<b>Parameter usage:</b>																							
<table><tr><td><b>Parameter:</b></td><td><b>Usage:</b></td></tr><tr><td>fNum</td><td>Specify a file number, which was used to open this communication port.</td></tr><tr><td>Mode</td><td>Specify the mode to which you would like to set CS-100A. If you would like to change multiple settings, you have to use this function multiple times/ <table><tr><td colspan="2"><b>Predefined values in cs100a_VBdeclares.bas: (cs100aMode Enumeration)</b></td></tr><tr><td><b>csPreset = 0</b></td><td><b>Set CS-100A to Minolta calibration mode</b></td></tr><tr><td><b>csVari = 1</b></td><td><b>Set CS-100A to user calibration mode</b></td></tr><tr><td><b>csAbs = 4</b></td><td><b>Set CS-100A to absolute measurement mode</b></td></tr><tr><td><b>csDiff = 5</b></td><td><b>Set CS-100A to difference measurement mode</b></td></tr><tr><td><b>csFast = 6</b></td><td><b>Set CS-100A to fast measurement mode Response time = 100 msec</b></td></tr><tr><td><b>csSlow = 7</b></td><td><b>Set CS-100A to slow measurement mode Response time = 400 msec</b></td></tr></table></td></tr></table>				<b>Parameter:</b>	<b>Usage:</b>	fNum	Specify a file number, which was used to open this communication port.	Mode	Specify the mode to which you would like to set CS-100A. If you would like to change multiple settings, you have to use this function multiple times/ <table><tr><td colspan="2"><b>Predefined values in cs100a_VBdeclares.bas: (cs100aMode Enumeration)</b></td></tr><tr><td><b>csPreset = 0</b></td><td><b>Set CS-100A to Minolta calibration mode</b></td></tr><tr><td><b>csVari = 1</b></td><td><b>Set CS-100A to user calibration mode</b></td></tr><tr><td><b>csAbs = 4</b></td><td><b>Set CS-100A to absolute measurement mode</b></td></tr><tr><td><b>csDiff = 5</b></td><td><b>Set CS-100A to difference measurement mode</b></td></tr><tr><td><b>csFast = 6</b></td><td><b>Set CS-100A to fast measurement mode Response time = 100 msec</b></td></tr><tr><td><b>csSlow = 7</b></td><td><b>Set CS-100A to slow measurement mode Response time = 400 msec</b></td></tr></table>	<b>Predefined values in cs100a_VBdeclares.bas: (cs100aMode Enumeration)</b>		<b>csPreset = 0</b>	<b>Set CS-100A to Minolta calibration mode</b>	<b>csVari = 1</b>	<b>Set CS-100A to user calibration mode</b>	<b>csAbs = 4</b>	<b>Set CS-100A to absolute measurement mode</b>	<b>csDiff = 5</b>	<b>Set CS-100A to difference measurement mode</b>	<b>csFast = 6</b>	<b>Set CS-100A to fast measurement mode Response time = 100 msec</b>	<b>csSlow = 7</b>	<b>Set CS-100A to slow measurement mode Response time = 400 msec</b>
<b>Parameter:</b>	<b>Usage:</b>																						
fNum	Specify a file number, which was used to open this communication port.																						
Mode	Specify the mode to which you would like to set CS-100A. If you would like to change multiple settings, you have to use this function multiple times/ <table><tr><td colspan="2"><b>Predefined values in cs100a_VBdeclares.bas: (cs100aMode Enumeration)</b></td></tr><tr><td><b>csPreset = 0</b></td><td><b>Set CS-100A to Minolta calibration mode</b></td></tr><tr><td><b>csVari = 1</b></td><td><b>Set CS-100A to user calibration mode</b></td></tr><tr><td><b>csAbs = 4</b></td><td><b>Set CS-100A to absolute measurement mode</b></td></tr><tr><td><b>csDiff = 5</b></td><td><b>Set CS-100A to difference measurement mode</b></td></tr><tr><td><b>csFast = 6</b></td><td><b>Set CS-100A to fast measurement mode Response time = 100 msec</b></td></tr><tr><td><b>csSlow = 7</b></td><td><b>Set CS-100A to slow measurement mode Response time = 400 msec</b></td></tr></table>	<b>Predefined values in cs100a_VBdeclares.bas: (cs100aMode Enumeration)</b>		<b>csPreset = 0</b>	<b>Set CS-100A to Minolta calibration mode</b>	<b>csVari = 1</b>	<b>Set CS-100A to user calibration mode</b>	<b>csAbs = 4</b>	<b>Set CS-100A to absolute measurement mode</b>	<b>csDiff = 5</b>	<b>Set CS-100A to difference measurement mode</b>	<b>csFast = 6</b>	<b>Set CS-100A to fast measurement mode Response time = 100 msec</b>	<b>csSlow = 7</b>	<b>Set CS-100A to slow measurement mode Response time = 400 msec</b>								
<b>Predefined values in cs100a_VBdeclares.bas: (cs100aMode Enumeration)</b>																							
<b>csPreset = 0</b>	<b>Set CS-100A to Minolta calibration mode</b>																						
<b>csVari = 1</b>	<b>Set CS-100A to user calibration mode</b>																						
<b>csAbs = 4</b>	<b>Set CS-100A to absolute measurement mode</b>																						
<b>csDiff = 5</b>	<b>Set CS-100A to difference measurement mode</b>																						
<b>csFast = 6</b>	<b>Set CS-100A to fast measurement mode Response time = 100 msec</b>																						
<b>csSlow = 7</b>	<b>Set CS-100A to slow measurement mode Response time = 400 msec</b>																						
<b>Return type and value:</b>																							
<table><tr><td><b>Data</b></td><td><b>Explanation</b></td></tr><tr><td>Long</td><td>Use for Error-Checking</td></tr><tr><td>0</td><td>No error</td></tr><tr><td>-11</td><td>ER11: Memory value Error!</td></tr><tr><td>-20</td><td>ER20: EEPROM Error!</td></tr><tr><td>-30</td><td>ER30: Low battery!</td></tr><tr><td>-103</td><td>Timeout: CS-100A didn't answer in proper time!</td></tr><tr><td>-104</td><td>Communication error: Please check for correct file number</td></tr><tr><td>-105</td><td>Command error: Wrong command or parameter was sent to CS-100A</td></tr><tr><td>-106</td><td>Parameter error: Wrong mode parameter was sent.</td></tr></table>				<b>Data</b>	<b>Explanation</b>	Long	Use for Error-Checking	0	No error	-11	ER11: Memory value Error!	-20	ER20: EEPROM Error!	-30	ER30: Low battery!	-103	Timeout: CS-100A didn't answer in proper time!	-104	Communication error: Please check for correct file number	-105	Command error: Wrong command or parameter was sent to CS-100A	-106	Parameter error: Wrong mode parameter was sent.
<b>Data</b>	<b>Explanation</b>																						
Long	Use for Error-Checking																						
0	No error																						
-11	ER11: Memory value Error!																						
-20	ER20: EEPROM Error!																						
-30	ER30: Low battery!																						
-103	Timeout: CS-100A didn't answer in proper time!																						
-104	Communication error: Please check for correct file number																						
-105	Command error: Wrong command or parameter was sent to CS-100A																						
-106	Parameter error: Wrong mode parameter was sent.																						
<b>Notes:</b>																							

<b>Function name:</b>  <b>cs100aMES</b>		<b>Library:</b> ls1x0cs100a.dll																													
<b>Function:</b> Take a <b>measurement</b> with connected CS-100A																															
<b>Declaration:</b> Public Declare Function cs100aMES Lib "ls1x0ls1x0cs100a.dll" (ByVal fNum As Integer, LY As Double, sx As Double, sy As Double) As Long																															
<b>Parameter:</b>																															
<table><tr><th>Pass by:</th><th>Name:</th><th>Data type:</th><th>Data range:</th></tr><tr><td>ByVal</td><td>fNum</td><td>Integer</td><td></td></tr><tr><td>ByRef</td><td>LY</td><td>Double</td><td></td></tr><tr><td>ByRef</td><td>sx</td><td>Double</td><td></td></tr><tr><td>ByRef</td><td>sy</td><td>Double</td><td></td></tr></table>				Pass by:	Name:	Data type:	Data range:	ByVal	fNum	Integer		ByRef	LY	Double		ByRef	sx	Double		ByRef	sy	Double									
Pass by:	Name:	Data type:	Data range:																												
ByVal	fNum	Integer																													
ByRef	LY	Double																													
ByRef	sx	Double																													
ByRef	sy	Double																													
<b>Parameter usage:</b>																															
<table><tr><th>Parameter:</th><th>Usage:</th></tr><tr><td>fNum</td><td>Specify a file number, which was used to open this communication port.</td></tr><tr><td>LY</td><td>Variable used to return the Y data of CS-100A</td></tr><tr><td>sx</td><td>Variable used to return the x data of CS-100A</td></tr><tr><td>sy</td><td>Variable used to return the y data of CS-100A</td></tr></table>				Parameter:	Usage:	fNum	Specify a file number, which was used to open this communication port.	LY	Variable used to return the Y data of CS-100A	sx	Variable used to return the x data of CS-100A	sy	Variable used to return the y data of CS-100A																		
Parameter:	Usage:																														
fNum	Specify a file number, which was used to open this communication port.																														
LY	Variable used to return the Y data of CS-100A																														
sx	Variable used to return the x data of CS-100A																														
sy	Variable used to return the y data of CS-100A																														
<b>Return type and value:</b>																															
<table><tr><th>Data</th><th>Explanation</th></tr><tr><td>Long</td><td>Use for Error-Checking</td></tr><tr><td>13</td><td>OK13: Luminance display range under!</td></tr><tr><td>12</td><td>OK12: Luminance display range over!</td></tr><tr><td>11</td><td>OK11: Chromaticity measuring range over!</td></tr><tr><td>0</td><td>No error</td></tr><tr><td>-10</td><td>ER10: Luminance and chromaticity range over!</td></tr><tr><td>-11</td><td>ER11: Memory value Error!</td></tr><tr><td>-12</td><td>ER12: Luminance and chromaticity simultaneous range over!</td></tr><tr><td>-20</td><td>ER20: EEPROM Error!</td></tr><tr><td>-30</td><td>ER30: Low battery!</td></tr><tr><td>-103</td><td>Timeout: CS-100A didn't answer in proper time!</td></tr><tr><td>-104</td><td>Communication error: Please check for correct file number</td></tr><tr><td>-105</td><td>Command error: Wrong command or parameter was sent to CS-100A</td></tr></table>				Data	Explanation	Long	Use for Error-Checking	13	OK13: Luminance display range under!	12	OK12: Luminance display range over!	11	OK11: Chromaticity measuring range over!	0	No error	-10	ER10: Luminance and chromaticity range over!	-11	ER11: Memory value Error!	-12	ER12: Luminance and chromaticity simultaneous range over!	-20	ER20: EEPROM Error!	-30	ER30: Low battery!	-103	Timeout: CS-100A didn't answer in proper time!	-104	Communication error: Please check for correct file number	-105	Command error: Wrong command or parameter was sent to CS-100A
Data	Explanation																														
Long	Use for Error-Checking																														
13	OK13: Luminance display range under!																														
12	OK12: Luminance display range over!																														
11	OK11: Chromaticity measuring range over!																														
0	No error																														
-10	ER10: Luminance and chromaticity range over!																														
-11	ER11: Memory value Error!																														
-12	ER12: Luminance and chromaticity simultaneous range over!																														
-20	ER20: EEPROM Error!																														
-30	ER30: Low battery!																														
-103	Timeout: CS-100A didn't answer in proper time!																														
-104	Communication error: Please check for correct file number																														
-105	Command error: Wrong command or parameter was sent to CS-100A																														
<b>Notes:</b>																															

<b>Function name:</b>  <b>cs100aRCR</b>		<b>Library:</b> ls1x0cs100a.dll																					
<b>Function:</b> <b>Re Calculate Reading of CS-100A according to mode setting</b>  You may use this command after sending mode change command. The CS-100A will return the re-calculated values of last measurement according to the new mode setting.																							
<b>Declaration:</b> Public Declare Function cs100aRCR Lib "ls1x0ls1x0cs100a.dll" (ByVal fNum As Integer, LY As Double, sx As Double, sy As Double) As Long																							
<b>Parameter:</b>																							
<table><tr><th>Pass by:</th><th>Name:</th><th>Data type:</th><th>Data range:</th></tr><tr><td>ByVal</td><td>fNum</td><td>Integer</td><td></td></tr><tr><td>ByRef</td><td>LY</td><td>Double</td><td></td></tr><tr><td>ByRef</td><td>sx</td><td>Double</td><td></td></tr><tr><td>ByRef</td><td>sy</td><td>Double</td><td></td></tr></table>				Pass by:	Name:	Data type:	Data range:	ByVal	fNum	Integer		ByRef	LY	Double		ByRef	sx	Double		ByRef	sy	Double	
Pass by:	Name:	Data type:	Data range:																				
ByVal	fNum	Integer																					
ByRef	LY	Double																					
ByRef	sx	Double																					
ByRef	sy	Double																					
<b>Parameter usage:</b>																							
<table><tr><th>Parameter:</th><th>Usage:</th></tr><tr><td>fNum</td><td>Specify a file number, which was used to open this communication port.</td></tr><tr><td>LY</td><td>Variable used to return the Y data of CS-100A</td></tr><tr><td>sx</td><td>Variable used to return the x data of CS-100A</td></tr><tr><td>sy</td><td>Variable used to return the y data of CS-100A</td></tr></table>				Parameter:	Usage:	fNum	Specify a file number, which was used to open this communication port.	LY	Variable used to return the Y data of CS-100A	sx	Variable used to return the x data of CS-100A	sy	Variable used to return the y data of CS-100A										
Parameter:	Usage:																						
fNum	Specify a file number, which was used to open this communication port.																						
LY	Variable used to return the Y data of CS-100A																						
sx	Variable used to return the x data of CS-100A																						
sy	Variable used to return the y data of CS-100A																						
<b>Return type and value:</b>																							
<table><tr><th>Data</th><th>Explanation</th></tr><tr><td>Long</td><td>Use for Error-Checking</td></tr><tr><td>0</td><td>No error</td></tr><tr><td>-11</td><td>ER11: Memory value Error!</td></tr><tr><td>-20</td><td>ER20: EEPROM Error!</td></tr><tr><td>-30</td><td>ER30: Low battery!</td></tr><tr><td>-103</td><td>Timeout: CS-100A didn't answer in proper time!</td></tr><tr><td>-104</td><td>Communication error: Please check for correct file number</td></tr><tr><td>-105</td><td>Command error: Wrong command or parameter was sent to CS-100A</td></tr></table>				Data	Explanation	Long	Use for Error-Checking	0	No error	-11	ER11: Memory value Error!	-20	ER20: EEPROM Error!	-30	ER30: Low battery!	-103	Timeout: CS-100A didn't answer in proper time!	-104	Communication error: Please check for correct file number	-105	Command error: Wrong command or parameter was sent to CS-100A		
Data	Explanation																						
Long	Use for Error-Checking																						
0	No error																						
-11	ER11: Memory value Error!																						
-20	ER20: EEPROM Error!																						
-30	ER30: Low battery!																						
-103	Timeout: CS-100A didn't answer in proper time!																						
-104	Communication error: Please check for correct file number																						
-105	Command error: Wrong command or parameter was sent to CS-100A																						
<b>Notes:</b>																							

<b>Function name:</b>  <b>cs100aTDR</b>		<b>Library:</b> ls1x0cs100a.dll																					
<b>Function:</b> Target Data Read from CS-100A																							
<b>Declaration:</b> Public Declare Function cs100aTDR Lib "ls1x0ls1x0cs100a.dll" (ByVal fNum As Integer, LY As Double, sx As Double, sy As Double) As Long																							
<b>Parameter:</b>																							
<table><tr><th>Pass by:</th><th>Name:</th><th>Data type:</th><th>Data range:</th></tr><tr><td>ByVal</td><td>fNum</td><td>Integer</td><td></td></tr><tr><td>ByRef</td><td>LY</td><td>Double</td><td></td></tr><tr><td>ByRef</td><td>sx</td><td>Double</td><td></td></tr><tr><td>ByRef</td><td>sy</td><td>Double</td><td></td></tr></table>				Pass by:	Name:	Data type:	Data range:	ByVal	fNum	Integer		ByRef	LY	Double		ByRef	sx	Double		ByRef	sy	Double	
Pass by:	Name:	Data type:	Data range:																				
ByVal	fNum	Integer																					
ByRef	LY	Double																					
ByRef	sx	Double																					
ByRef	sy	Double																					
<b>Parameter usage:</b>																							
<table><tr><th>Parameter:</th><th>Usage:</th></tr><tr><td>fNum</td><td>Specify a file number, which was used to open this communication port.</td></tr><tr><td>LY</td><td>Variable used to return the Y target data of CS-100A</td></tr><tr><td>sx</td><td>Variable used to return the x target data of CS-100A</td></tr><tr><td>sy</td><td>Variable used to return the y target data of CS-100A</td></tr></table>				Parameter:	Usage:	fNum	Specify a file number, which was used to open this communication port.	LY	Variable used to return the Y target data of CS-100A	sx	Variable used to return the x target data of CS-100A	sy	Variable used to return the y target data of CS-100A										
Parameter:	Usage:																						
fNum	Specify a file number, which was used to open this communication port.																						
LY	Variable used to return the Y target data of CS-100A																						
sx	Variable used to return the x target data of CS-100A																						
sy	Variable used to return the y target data of CS-100A																						
<b>Return type and value:</b>																							
<table><tr><th>Data</th><th>Explanation</th></tr><tr><td>Long</td><td>Use for Error-Checking</td></tr><tr><td>0</td><td>No error</td></tr><tr><td>-11</td><td>ER11: Memory value Error!</td></tr><tr><td>-20</td><td>ER20: EEPROM Error!</td></tr><tr><td>-30</td><td>ER30: Low battery!</td></tr><tr><td>-103</td><td>Timeout: CS-100A didn't answer in proper time!</td></tr><tr><td>-104</td><td>Communication error: Please check for correct file number</td></tr><tr><td>-105</td><td>Command error: Wrong command or parameter was sent to CS-100A</td></tr></table>				Data	Explanation	Long	Use for Error-Checking	0	No error	-11	ER11: Memory value Error!	-20	ER20: EEPROM Error!	-30	ER30: Low battery!	-103	Timeout: CS-100A didn't answer in proper time!	-104	Communication error: Please check for correct file number	-105	Command error: Wrong command or parameter was sent to CS-100A		
Data	Explanation																						
Long	Use for Error-Checking																						
0	No error																						
-11	ER11: Memory value Error!																						
-20	ER20: EEPROM Error!																						
-30	ER30: Low battery!																						
-103	Timeout: CS-100A didn't answer in proper time!																						
-104	Communication error: Please check for correct file number																						
-105	Command error: Wrong command or parameter was sent to CS-100A																						
<b>Notes:</b>																							

<b>Function name:</b>  <b>cs100aTDS</b>		<b>Library:</b> ls1x0cs100a.dll																		
<b>Function:</b> Target Data Set to CS-100A  This function is used to store the actual measuring data of CS-100A into the target memory. Function is same like switching CS-100A from ABS to DIFF while pressing the F key.																				
<b>Declaration:</b> Public Declare Function cs100aTDS Lib "ls1x0cs100a.dll" (ByVal fNum As Integer) As Long																				
<b>Parameter:</b>																				
		<table><tr><th>Pass by:</th><th>Name:</th><th>Data type:</th><th>Data range:</th></tr><tr><td>ByVal</td><td>fNum</td><td>Integer</td><td></td></tr></table>	Pass by:	Name:	Data type:	Data range:	ByVal	fNum	Integer											
Pass by:	Name:	Data type:	Data range:																	
ByVal	fNum	Integer																		
<b>Parameter usage:</b>																				
		<table><tr><th>Parameter:</th><th>Usage:</th></tr><tr><td>fNum</td><td>Specify a file number, which was used to open this communication port.</td></tr></table>	Parameter:	Usage:	fNum	Specify a file number, which was used to open this communication port.														
Parameter:	Usage:																			
fNum	Specify a file number, which was used to open this communication port.																			
<b>Return type and value:</b>																				
		<table><tr><th>Data</th><th>Explanation</th></tr><tr><td>Long</td><td>Use for Error-Checking</td></tr><tr><td>0</td><td>No error</td></tr><tr><td>-11</td><td>ER11: Memory value Error!</td></tr><tr><td>-20</td><td>ER20: EEPROM Error!</td></tr><tr><td>-30</td><td>ER30: Low battery!</td></tr><tr><td>-103</td><td>Timeout: CS-100A didn't answer in proper time!</td></tr><tr><td>-104</td><td>Communication error: Please check for correct file number</td></tr><tr><td>-105</td><td>Command error: Wrong command or parameter was sent to CS-100A</td></tr></table>	Data	Explanation	Long	Use for Error-Checking	0	No error	-11	ER11: Memory value Error!	-20	ER20: EEPROM Error!	-30	ER30: Low battery!	-103	Timeout: CS-100A didn't answer in proper time!	-104	Communication error: Please check for correct file number	-105	Command error: Wrong command or parameter was sent to CS-100A
Data	Explanation																			
Long	Use for Error-Checking																			
0	No error																			
-11	ER11: Memory value Error!																			
-20	ER20: EEPROM Error!																			
-30	ER30: Low battery!																			
-103	Timeout: CS-100A didn't answer in proper time!																			
-104	Communication error: Please check for correct file number																			
-105	Command error: Wrong command or parameter was sent to CS-100A																			
<b>Notes:</b>																				

<b>Function name:</b>  <b>cs100aTDW</b>		<b>Library:</b> ls1x0cs100a.dll																					
<b>Function:</b> Target Data Write to CS-100A  By using this function you can send your own target data (Yxy) to CS-100A																							
<b>Declaration:</b> Public Declare Function cs100aTDW Lib "ls1x0cs100a.dll" (ByVal fNum As Integer, ByVal LY As Double, ByVal sx As Double, ByVal sy As Double) As Long																							
<b>Parameter:</b> <table><tr><th>Pass by:</th><th>Name:</th><th>Data type:</th><th>Data range:</th></tr><tr><td>ByVal</td><td>fNum</td><td>Integer</td><td></td></tr><tr><td>ByVal</td><td>LY</td><td>Double</td><td></td></tr><tr><td>ByVal</td><td>sx</td><td>Double</td><td></td></tr><tr><td>ByVal</td><td>sy</td><td>Double</td><td></td></tr></table>				Pass by:	Name:	Data type:	Data range:	ByVal	fNum	Integer		ByVal	LY	Double		ByVal	sx	Double		ByVal	sy	Double	
Pass by:	Name:	Data type:	Data range:																				
ByVal	fNum	Integer																					
ByVal	LY	Double																					
ByVal	sx	Double																					
ByVal	sy	Double																					
<b>Parameter usage:</b> <table><tr><th>Parameter:</th><th>Usage:</th></tr><tr><td>Fnum</td><td>Specify a file number, which was used to open this communication port.</td></tr><tr><td>LY</td><td>Y target data</td></tr><tr><td>Sx</td><td>x target data</td></tr><tr><td>Sy</td><td>y target data</td></tr></table>				Parameter:	Usage:	Fnum	Specify a file number, which was used to open this communication port.	LY	Y target data	Sx	x target data	Sy	y target data										
Parameter:	Usage:																						
Fnum	Specify a file number, which was used to open this communication port.																						
LY	Y target data																						
Sx	x target data																						
Sy	y target data																						
<b>Return type and value:</b> <table><tr><th>Data</th><th>Explanation</th></tr><tr><td>Long</td><td>Use for Error-Checking</td></tr><tr><td>0</td><td>No error</td></tr><tr><td>-11</td><td>ER11: Memory value Error!</td></tr><tr><td>-20</td><td>ER20: EEPROM Error!</td></tr><tr><td>-30</td><td>ER30: Low battery!</td></tr><tr><td>-103</td><td>Timeout: CS-100A didn't answer in proper time!</td></tr><tr><td>-104</td><td>Communication error: Please check for correct file number</td></tr><tr><td>-105</td><td>Command error: Wrong command or parameter was sent to CS-100A</td></tr></table>				Data	Explanation	Long	Use for Error-Checking	0	No error	-11	ER11: Memory value Error!	-20	ER20: EEPROM Error!	-30	ER30: Low battery!	-103	Timeout: CS-100A didn't answer in proper time!	-104	Communication error: Please check for correct file number	-105	Command error: Wrong command or parameter was sent to CS-100A		
Data	Explanation																						
Long	Use for Error-Checking																						
0	No error																						
-11	ER11: Memory value Error!																						
-20	ER20: EEPROM Error!																						
-30	ER30: Low battery!																						
-103	Timeout: CS-100A didn't answer in proper time!																						
-104	Communication error: Please check for correct file number																						
-105	Command error: Wrong command or parameter was sent to CS-100A																						
<b>Notes:</b>																							

<b>Function name:</b>  <b>cs100aUCR</b>		<b>Library:</b> ls1x0cs100a.dll																					
<b>Function:</b> User Calibration Read from CS-100A  This function returns the user calibration data memorized in CS-100A																							
<b>Declaration:</b> Public Declare Function cs100aUCR Lib "ls1x0cs100a.dll" (ByVal fNum As Integer, LY As Double, sx As Double, sy As Double) As Long																							
<b>Parameter:</b>																							
<table><tr><th>Pass by:</th><th>Name:</th><th>Data type:</th><th>Data range:</th></tr><tr><td>ByVal</td><td>fNum</td><td>Integer</td><td></td></tr><tr><td>ByRef</td><td>LY</td><td>Double</td><td></td></tr><tr><td>ByRef</td><td>sx</td><td>Double</td><td></td></tr><tr><td>ByRef</td><td>sy</td><td>Double</td><td></td></tr></table>				Pass by:	Name:	Data type:	Data range:	ByVal	fNum	Integer		ByRef	LY	Double		ByRef	sx	Double		ByRef	sy	Double	
Pass by:	Name:	Data type:	Data range:																				
ByVal	fNum	Integer																					
ByRef	LY	Double																					
ByRef	sx	Double																					
ByRef	sy	Double																					
<b>Parameter usage:</b>																							
<table><tr><th>Parameter:</th><th>Usage:</th></tr><tr><td>Fnum</td><td>Specify a file number, which was used to open this communication port.</td></tr><tr><td>LY</td><td>Y User calibration data</td></tr><tr><td>Sx</td><td>x User calibration data</td></tr><tr><td>Sy</td><td>y User calibration data</td></tr></table>				Parameter:	Usage:	Fnum	Specify a file number, which was used to open this communication port.	LY	Y User calibration data	Sx	x User calibration data	Sy	y User calibration data										
Parameter:	Usage:																						
Fnum	Specify a file number, which was used to open this communication port.																						
LY	Y User calibration data																						
Sx	x User calibration data																						
Sy	y User calibration data																						
<b>Return type and value:</b>																							
<table><tr><th>Data</th><th>Explanation</th></tr><tr><td>Long</td><td>Use for Error-Checking</td></tr><tr><td>0</td><td>No error</td></tr><tr><td>-11</td><td>ER11: Memory value Error!</td></tr><tr><td>-20</td><td>ER20: EEPROM Error!</td></tr><tr><td>-30</td><td>ER30: Low battery!</td></tr><tr><td>-103</td><td>Timeout: CS-100A didn't answer in proper time!</td></tr><tr><td>-104</td><td>Communication error: Please check for correct file number</td></tr><tr><td>-105</td><td>Command error: Wrong command or parameter was sent to CS-100A</td></tr></table>				Data	Explanation	Long	Use for Error-Checking	0	No error	-11	ER11: Memory value Error!	-20	ER20: EEPROM Error!	-30	ER30: Low battery!	-103	Timeout: CS-100A didn't answer in proper time!	-104	Communication error: Please check for correct file number	-105	Command error: Wrong command or parameter was sent to CS-100A		
Data	Explanation																						
Long	Use for Error-Checking																						
0	No error																						
-11	ER11: Memory value Error!																						
-20	ER20: EEPROM Error!																						
-30	ER30: Low battery!																						
-103	Timeout: CS-100A didn't answer in proper time!																						
-104	Communication error: Please check for correct file number																						
-105	Command error: Wrong command or parameter was sent to CS-100A																						
<b>Notes:</b>																							



<b>Function name:</b>  <b>cs100aUCW</b>		<b>Library:</b> ls1x0cs100a.dll																				
<b>Function:</b> User Calibration Write to CS-100A  This function writes your user calibration data into CS-100A memory.																						
<b>Declaration:</b> Public Declare Function cs100aUCW Lib "ls1x0cs100a.dll" (ByVal fNum As Integer, ByVal LY As Double, ByVal sx As Double, ByVal sy As Double) As Long																						
<b>Parameter:</b> <table><tr><th>Pass by:</th><th>Name:</th><th>Data type:</th><th>Data range:</th></tr><tr><td>ByVal</td><td>fNum</td><td>Integer</td><td></td></tr><tr><td>ByRef</td><td>LY</td><td>Double</td><td></td></tr><tr><td>ByRef</td><td>sx</td><td>Double</td><td></td></tr><tr><td>ByRef</td><td>sy</td><td>Double</td><td></td></tr></table>			Pass by:	Name:	Data type:	Data range:	ByVal	fNum	Integer		ByRef	LY	Double		ByRef	sx	Double		ByRef	sy	Double	
Pass by:	Name:	Data type:	Data range:																			
ByVal	fNum	Integer																				
ByRef	LY	Double																				
ByRef	sx	Double																				
ByRef	sy	Double																				
<b>Parameter usage:</b> <table><tr><th>Parameter:</th><th>Usage:</th></tr><tr><td>Fnum</td><td>Specify a file number, which was used to open this communication port.</td></tr><tr><td>LY</td><td>Y User calibration data</td></tr><tr><td>Sx</td><td>x User calibration data</td></tr><tr><td>Sy</td><td>y User calibration data</td></tr></table>			Parameter:	Usage:	Fnum	Specify a file number, which was used to open this communication port.	LY	Y User calibration data	Sx	x User calibration data	Sy	y User calibration data										
Parameter:	Usage:																					
Fnum	Specify a file number, which was used to open this communication port.																					
LY	Y User calibration data																					
Sx	x User calibration data																					
Sy	y User calibration data																					
<b>Return type and value:</b> <table><tr><th>Data</th><th>Explanation</th></tr><tr><td>Long</td><td>Use for Error-Checking</td></tr><tr><td>0</td><td>No error</td></tr><tr><td>-11</td><td>ER11: Memory value Error!</td></tr><tr><td>-20</td><td>ER20: EEPROM Error!</td></tr><tr><td>-30</td><td>ER30: Low battery!</td></tr><tr><td>-103</td><td>Timeout: CS-100A didn't answer in proper time!</td></tr><tr><td>-104</td><td>Communication error: Please check for correct file number</td></tr><tr><td>-105</td><td>Command error: Wrong command or parameter was sent to CS-100A</td></tr></table>			Data	Explanation	Long	Use for Error-Checking	0	No error	-11	ER11: Memory value Error!	-20	ER20: EEPROM Error!	-30	ER30: Low battery!	-103	Timeout: CS-100A didn't answer in proper time!	-104	Communication error: Please check for correct file number	-105	Command error: Wrong command or parameter was sent to CS-100A		
Data	Explanation																					
Long	Use for Error-Checking																					
0	No error																					
-11	ER11: Memory value Error!																					
-20	ER20: EEPROM Error!																					
-30	ER30: Low battery!																					
-103	Timeout: CS-100A didn't answer in proper time!																					
-104	Communication error: Please check for correct file number																					
-105	Command error: Wrong command or parameter was sent to CS-100A																					
<b>Notes:</b> <b>Please keep in mind that this user calibration data is in relation to the actual measurement data in CS-100A. When performing user calibration, you first have to measure the light source in Minolta calibration mode and then you may send your corrected values!!</b>																						

## LS-1x0 support functions

Please see the following list of commands available by LS-1x0

Command	Function	Page
CLE	Clears the memory of LS-1x0	
MDS	Mode setting like absolute or difference measurement, fast or slow measurement mode and user calibration	
MES	Taking measurement according to the settings defined by MDS command	
DSR	Read the displayed data in memory according to the settings made by MDS command	
CMR	Read target data, which is stored in LS-1x0 for difference measurements.	
CMS	Set the measured value into target memory of LS-1x0	
CMW	Write target values into LS-1x0 memory	
LMR	Read the standard value for measuring user calibration standard which is memorized in LS-1x0	
LMW	Write the standard value for measuring user calibration standard into LS-1x0 memory	
CCR	Read the Color Correction Factor which is memorized in LS-1x0	
CCW	Write the Color Correction Factor into LS-1x0 memory	

<b>Function name:</b>  <b>Ls100CLE</b>		<b>Library:</b> 1x0cs100a.dll																			
<b>Function:</b> Clears the memory of connected LS-1x0																					
<b>Declaration:</b> Public Declare Function Ls100CLE Lib "ls1x0ls1x0cs100a.dll" (ByVal fNum As Integer) As Long																					
<b>Parameter:</b>																					
<table><tr><td><b>Pass by:</b></td><td><b>Name:</b></td><td><b>Data type:</b></td><td><b>Data range:</b></td></tr><tr><td>ByVal</td><td>FNum</td><td>Integer</td><td></td></tr></table>		<b>Pass by:</b>	<b>Name:</b>	<b>Data type:</b>	<b>Data range:</b>	ByVal	FNum	Integer													
<b>Pass by:</b>	<b>Name:</b>	<b>Data type:</b>	<b>Data range:</b>																		
ByVal	FNum	Integer																			
<b>Parameter usage:</b>																					
<table><tr><td><b>Parameter:</b></td><td><b>Usage:</b></td></tr><tr><td>fNum</td><td>Specify a file number, which was used to open this communication port.</td></tr></table>		<b>Parameter:</b>	<b>Usage:</b>	fNum	Specify a file number, which was used to open this communication port.																
<b>Parameter:</b>	<b>Usage:</b>																				
fNum	Specify a file number, which was used to open this communication port.																				
<b>Return type and value:</b>																					
<table><tr><td><b>Data</b></td><td><b>Explanation</b></td></tr><tr><td>Long</td><td>Use for Error-Checking</td></tr><tr><td>0</td><td>No error</td></tr><tr><td>-11</td><td>ER11: Memory value Error!</td></tr><tr><td>-20</td><td>ER20: EEPROM Error!</td></tr><tr><td>-30</td><td>ER30: Low battery!</td></tr><tr><td>-103</td><td>Time out: LS-1x0 didn't answer in proper time!</td></tr><tr><td>-104</td><td>Communication error: Please check for correct file number</td></tr><tr><td>-105</td><td>Command error: Wrong command or parameter was sent to CS-100A</td></tr></table>		<b>Data</b>	<b>Explanation</b>	Long	Use for Error-Checking	0	No error	-11	ER11: Memory value Error!	-20	ER20: EEPROM Error!	-30	ER30: Low battery!	-103	Time out: LS-1x0 didn't answer in proper time!	-104	Communication error: Please check for correct file number	-105	Command error: Wrong command or parameter was sent to CS-100A		
<b>Data</b>	<b>Explanation</b>																				
Long	Use for Error-Checking																				
0	No error																				
-11	ER11: Memory value Error!																				
-20	ER20: EEPROM Error!																				
-30	ER30: Low battery!																				
-103	Time out: LS-1x0 didn't answer in proper time!																				
-104	Communication error: Please check for correct file number																				
-105	Command error: Wrong command or parameter was sent to CS-100A																				
<b>Notes:</b>																					

Function name:			Library:
Ls100MDS			1x0cs100a.dll
Function:			
Mode setting			
Declaration: Visual Basic for Application – Ex: EXCEL (no Enum)			
Public Declare Function Ls100MDS Lib "ls1x0ls1x0cs100a.dll" (ByVal fNum As Integer, ByVal Mode As Integer) As Long			
Declaration: Visual Basic (with Enum)			
Public Declare Function Ls100aMDS Lib "ls1x0ls1x0cs100a.dll" (ByVal fNum As Integer, ByVal Mode As Ls1x0Mode) As Long			
Parameter:			
	Pass by:	Name:	Data type:
	ByVal	FNum	Integer
	ByVal	Mode	Integer
			0,1,4-7
Parameter usage:			
	Parameter:	Usage:	
	FNum	Specify a file number, which was used to open this communication port.	
	Mode	Specify the mode to which you would like to set LS-1x0. If you would like to change multiple settings, you have to use this function multiple times/	
		Predefined values in ls100_VBdeclares.bas: (Ls100Mode Enumeration)	
		LsPreset = 0	Set LS-1x0 to Minolta calibration mode
		LsVariCCF = 1	Set LS-1x0 to CCF mode
		LsVariLUMI = 2	Set LS-1x0 to user calibration mode
		LsVariCCFLUMI = 3	Set LS-1x0 to user calibration & CCF mode
		LsAbs = 4	Set LS-1x0 to absolute measurement mode
		LsDiff = 5	Set LS-1x0 to difference measurement mode
		LsFast = 6	Set LS-1x0 to fast measurement mode Response time = 200 msec
		LsSlow = 7	Set LS-1x0 to slow measurement mode Response time = 400 msec
		LsPEAK = 8	Set LS-1x0 to PEAK measurement mode. (Only possible to reset by switching off LS1x0
		LsCONT = 9	Set LS-1x0 to CONTINUOUS measurement mode.
Return type and value:			
	Data	Explanation	
	Long	Use for Error-Checking	
	0	No error	
	-11	ER11: Memory value Error!	
	-20	ER20: EEPROM Error!	
	-30	ER30: Low battery!	
	-103	Time out: LS-1x0 didn't answer in proper time!	
	-104	Communication error: Please check for correct file number	
	-105	Command error: Wrong command or parameter was sent to LS-1x0	
	-106	Parameter error: Wrong mode parameter was sent.	
Notes:			

<b>Function name:</b>		<b>Library:</b>	
<b>Is100MES</b>		1x0cs100a.dll	
<b>Function:</b>			
Take a <b>measurement</b> with connected LS-1x0			
<b>Declaration:</b>			
Public Declare Function Is100MES Lib "Is1x0ls1x0cs100a.dll" (ByVal fNum As Integer, PeakMode as integer, Unit as integer, VARI as integer, LY As Double) As Long			
<b>Parameter:</b>			
<b>Pass by:</b>	<b>Name:</b>	<b>Data type:</b>	<b>Data range:</b>
ByVal	Fnum	Integer	
ByRef	PeakMode	Integer	
ByRef	Unit	Integer	
ByRef	Vari	Integer	
ByRef	LY	Double	
<b>Parameter usage:</b>			
<b>Parameter:</b>	<b>Usage:</b>		
fNum	Specify a file number, which was used to open this communication port.		
PeakMode	Flag showing Peak mode (0 = Continuous 1 = Peak)		
Unit	Measurement unit (0 = cd/m <sup>2</sup> 1 = fL)		
Vari	User calibration flag: 0 = Preset 1 = Vari CCF 2 = Vari LUMI 3 = Vari CCF & LUMI 4 = Difference mode		
LY	Variable used to return the Y data of LS-1x0		
<b>Return type and value:</b>			
<b>Data</b>	<b>Explanation</b>		
Long	Use for Error-Checking		
13	OK13: Luminance display range under!		
12	OK12: Luminance display range over!		
11	OK11: Chromaticity measuring range over!		
0	No error		
-10	ER10: Luminance and chromaticity range over!		
-11	ER11: Memory value Error!		
-12	ER12: Luminance and chromaticity simultaneous range over!		
-20	ER20: EEPROM Error!		
-30	ER30: Low battery!		
-103	Time out: LS-1x0 didn't answer in proper time!		
-104	Communication error: Please check for correct file number		
-105	Command error: Wrong command or parameter was sent to LS-1x0		
<b>Notes:</b>			

<b>Function name:</b>		<b>Library:</b>																									
<b>Is100DSR</b>		1x0cs100a.dll																									
<b>Function:</b>																											
Display Setting Read of LS-1x0 according to mode setting You may use this command after sending mode change command. The LS-1x0 will return the re-calculated values of last measurement according to the new mode setting.																											
<b>Declaration:</b>																											
Public Declare Function Is100DSR Lib "Is1x0ls1x0cs100a.dll" (ByVal fNum As Integer, PeakMode as integer, Unit as integer, VARI as integer, LY As Double) As Long																											
<b>Parameter:</b>																											
<table><tr><th>Pass by:</th><th>Name:</th><th>Data type:</th><th>Data range:</th></tr><tr><td>ByVal</td><td>Fnum</td><td>Integer</td><td></td></tr><tr><td>ByRef</td><td>PeakMode</td><td>Integer</td><td></td></tr><tr><td>ByRef</td><td>Unit</td><td>Integer</td><td></td></tr><tr><td>ByRef</td><td>Vari</td><td>Integer</td><td></td></tr><tr><td>ByRef</td><td>LY</td><td>Double</td><td></td></tr></table>				Pass by:	Name:	Data type:	Data range:	ByVal	Fnum	Integer		ByRef	PeakMode	Integer		ByRef	Unit	Integer		ByRef	Vari	Integer		ByRef	LY	Double	
Pass by:	Name:	Data type:	Data range:																								
ByVal	Fnum	Integer																									
ByRef	PeakMode	Integer																									
ByRef	Unit	Integer																									
ByRef	Vari	Integer																									
ByRef	LY	Double																									
<b>Parameter usage:</b>																											
<table><tr><th>Parameter:</th><th>Usage:</th></tr><tr><td>fNum</td><td>Specify a file number, which was used to open this communication port.</td></tr><tr><td>PeakMode</td><td>Flag showing Peak mode (0 = Continuous 1 = Peak)</td></tr><tr><td>Unit</td><td>Measurement unit (0 = cd/m<sup>2</sup> 1 = fL)</td></tr><tr><td>Vari</td><td>User calibration flag: 0 = Preset 1 = Vari CCF 2 = Vari LUMI 3 = Vari CCF &amp; LUMI 4 = Difference mode</td></tr><tr><td>LY</td><td>Variable used to return the Y data of LS-1x0</td></tr></table>				Parameter:	Usage:	fNum	Specify a file number, which was used to open this communication port.	PeakMode	Flag showing Peak mode (0 = Continuous 1 = Peak)	Unit	Measurement unit (0 = cd/m <sup>2</sup> 1 = fL)	Vari	User calibration flag: 0 = Preset 1 = Vari CCF 2 = Vari LUMI 3 = Vari CCF & LUMI 4 = Difference mode	LY	Variable used to return the Y data of LS-1x0												
Parameter:	Usage:																										
fNum	Specify a file number, which was used to open this communication port.																										
PeakMode	Flag showing Peak mode (0 = Continuous 1 = Peak)																										
Unit	Measurement unit (0 = cd/m <sup>2</sup> 1 = fL)																										
Vari	User calibration flag: 0 = Preset 1 = Vari CCF 2 = Vari LUMI 3 = Vari CCF & LUMI 4 = Difference mode																										
LY	Variable used to return the Y data of LS-1x0																										
<b>Return type and value:</b>																											
<table><tr><th>Data</th><th>Explanation</th></tr><tr><td>Long</td><td>Use for Error-Checking</td></tr><tr><td>0</td><td>No error</td></tr><tr><td>-11</td><td>ER11: Memory value Error!</td></tr><tr><td>-20</td><td>ER20: EEPROM Error!</td></tr><tr><td>-30</td><td>ER30: Low battery!</td></tr><tr><td>-103</td><td>Time out: LS-1x0 didn't answer in proper time!</td></tr><tr><td>-104</td><td>Communication error: Please check for correct file number</td></tr><tr><td>-105</td><td>Command error: Wrong command or parameter was sent to LS-1x0</td></tr></table>				Data	Explanation	Long	Use for Error-Checking	0	No error	-11	ER11: Memory value Error!	-20	ER20: EEPROM Error!	-30	ER30: Low battery!	-103	Time out: LS-1x0 didn't answer in proper time!	-104	Communication error: Please check for correct file number	-105	Command error: Wrong command or parameter was sent to LS-1x0						
Data	Explanation																										
Long	Use for Error-Checking																										
0	No error																										
-11	ER11: Memory value Error!																										
-20	ER20: EEPROM Error!																										
-30	ER30: Low battery!																										
-103	Time out: LS-1x0 didn't answer in proper time!																										
-104	Communication error: Please check for correct file number																										
-105	Command error: Wrong command or parameter was sent to LS-1x0																										
<b>Notes:</b>																											

<b>Function name:</b>		<b>Library:</b> 1x0cs100a.dll																			
<b>Is100CMR</b>																					
<b>Function:</b> Custom Mean Read from LS-1x0																					
<b>Declaration:</b> Public Declare Function Is100CMR Lib "Is1x0Is1x0cs100a.dll" (ByVal fNum As Integer, Unit as integer, LY As Double) As Long																					
<b>Parameter:</b>																					
<table><tr><th>Pass by:</th><th>Name:</th><th>Data type:</th><th>Data range:</th></tr><tr><td>ByVal</td><td>fNum</td><td>Integer</td><td></td></tr><tr><td>ByRef</td><td>Unit</td><td>Integer</td><td></td></tr><tr><td>ByRef</td><td>LY</td><td>Double</td><td></td></tr></table>				Pass by:	Name:	Data type:	Data range:	ByVal	fNum	Integer		ByRef	Unit	Integer		ByRef	LY	Double			
Pass by:	Name:	Data type:	Data range:																		
ByVal	fNum	Integer																			
ByRef	Unit	Integer																			
ByRef	LY	Double																			
<b>Parameter usage:</b>																					
<table><tr><th>Parameter:</th><th>Usage:</th></tr><tr><td>fNum</td><td>Specify a file number, which was used to open this communication port.</td></tr><tr><td>Unit</td><td>Measurement unit (0 = cd/m<sup>2</sup> 1 = fL)</td></tr><tr><td>LY</td><td><ul style="list-style-type: none"><li>Variable used to return the Y target data of LS-1x0</li></ul></td></tr></table>				Parameter:	Usage:	fNum	Specify a file number, which was used to open this communication port.	Unit	Measurement unit (0 = cd/m <sup>2</sup> 1 = fL)	LY	<ul style="list-style-type: none"><li>Variable used to return the Y target data of LS-1x0</li></ul>										
Parameter:	Usage:																				
fNum	Specify a file number, which was used to open this communication port.																				
Unit	Measurement unit (0 = cd/m <sup>2</sup> 1 = fL)																				
LY	<ul style="list-style-type: none"><li>Variable used to return the Y target data of LS-1x0</li></ul>																				
<b>Return type and value:</b>																					
<table><tr><th>Data</th><th>Explanation</th></tr><tr><td>Long</td><td>Use for Error-Checking</td></tr><tr><td>0</td><td>No error</td></tr><tr><td>-11</td><td>ER11: Memory value Error!</td></tr><tr><td>-20</td><td>ER20: EEPROM Error!</td></tr><tr><td>-30</td><td>ER30: Low battery!</td></tr><tr><td>-103</td><td>Time out: LS-1x0 didn't answer in proper time!</td></tr><tr><td>-104</td><td>Communication error: Please check for correct file number</td></tr><tr><td>-105</td><td>Command error: Wrong command or parameter was sent to LS-1x0</td></tr></table>				Data	Explanation	Long	Use for Error-Checking	0	No error	-11	ER11: Memory value Error!	-20	ER20: EEPROM Error!	-30	ER30: Low battery!	-103	Time out: LS-1x0 didn't answer in proper time!	-104	Communication error: Please check for correct file number	-105	Command error: Wrong command or parameter was sent to LS-1x0
Data	Explanation																				
Long	Use for Error-Checking																				
0	No error																				
-11	ER11: Memory value Error!																				
-20	ER20: EEPROM Error!																				
-30	ER30: Low battery!																				
-103	Time out: LS-1x0 didn't answer in proper time!																				
-104	Communication error: Please check for correct file number																				
-105	Command error: Wrong command or parameter was sent to LS-1x0																				
<b>Notes:</b>																					

<b>Function name:</b>		<b>Library:</b>	
Is100CMS		ls1x0cs100a.dll	
<b>Function:</b>			
Custom Mean Set to LS-1x0			
This function is used to store the actual measuring data of LS-1x0 into the target memory. Function is same like switching LS-1x0 from ABS to DIFF while pressing the F key.			
<b>Declaration:</b>			
Public Declare Function Is100CMS Lib "ls1x0cs100a.dll" (ByVal fNum As Integer) As Long			
<b>Parameter:</b>			
<b>Pass by:</b>	<b>Name:</b>	<b>Data type:</b>	<b>Data range:</b>
ByVal	fNum	Integer	
<b>Parameter usage:</b>			
<b>Parameter:</b>	<b>Usage:</b>		
fNum	Specify a file number, which was used to open this communication port.		
<b>Return type and value:</b>			
<b>Data</b>	<b>Explanation</b>		
Long	Use for Error-Checking		
0	No error		
-11	ER11: Memory value Error!		
-20	ER20: EEPROM Error!		
-30	ER30: Low battery!		
-103	Time out: LS-1x0 didn't answer in proper time!		
-104	Communication error: Please check for correct file number		
-105	Command error: Wrong command or parameter was sent to LS-1x0		
<b>Notes:</b>			



<b>Function name:</b> <b>Is100CMW</b>		<b>Library:</b> ls1x0cs100a.dll																			
<b>Function:</b> Custom Mean Write to LS-1x0  By using this function you can send your own target data (Y) to LS-1x0																					
<b>Declaration:</b> Public Declare Function Is100CMW Lib "ls1x0cs100a.dll" (ByVal fNum As Integer, ByVal LY As Double) As Long																					
<b>Parameter:</b> <table><tr><th>Pass by:</th><th>Name:</th><th>Data type:</th><th>Data range:</th></tr><tr><td>ByVal</td><td>fNum</td><td>Integer</td><td></td></tr><tr><td>ByVal</td><td>LY</td><td>Double</td><td></td></tr></table>				Pass by:	Name:	Data type:	Data range:	ByVal	fNum	Integer		ByVal	LY	Double							
Pass by:	Name:	Data type:	Data range:																		
ByVal	fNum	Integer																			
ByVal	LY	Double																			
<b>Parameter usage:</b> <table><tr><th>Parameter:</th><th>Usage:</th></tr><tr><td>Fnum</td><td>Specify a file number, which was used to open this communication port.</td></tr><tr><td>LY</td><td>Y target data</td></tr></table>				Parameter:	Usage:	Fnum	Specify a file number, which was used to open this communication port.	LY	Y target data												
Parameter:	Usage:																				
Fnum	Specify a file number, which was used to open this communication port.																				
LY	Y target data																				
<b>Return type and value:</b> <table><tr><th>Data</th><th>Explanation</th></tr><tr><td>Long</td><td>Use for Error-Checking</td></tr><tr><td>0</td><td>No error</td></tr><tr><td>-11</td><td>ER11: Memory value Error!</td></tr><tr><td>-20</td><td>ER20: EEPROM Error!</td></tr><tr><td>-30</td><td>ER30: Low battery!</td></tr><tr><td>-103</td><td>Time out: LS-1x0 didn't answer in proper time!</td></tr><tr><td>-104</td><td>Communication error: Please check for correct file number</td></tr><tr><td>-105</td><td>Command error: Wrong command or parameter was sent to LS-1x0</td></tr></table>				Data	Explanation	Long	Use for Error-Checking	0	No error	-11	ER11: Memory value Error!	-20	ER20: EEPROM Error!	-30	ER30: Low battery!	-103	Time out: LS-1x0 didn't answer in proper time!	-104	Communication error: Please check for correct file number	-105	Command error: Wrong command or parameter was sent to LS-1x0
Data	Explanation																				
Long	Use for Error-Checking																				
0	No error																				
-11	ER11: Memory value Error!																				
-20	ER20: EEPROM Error!																				
-30	ER30: Low battery!																				
-103	Time out: LS-1x0 didn't answer in proper time!																				
-104	Communication error: Please check for correct file number																				
-105	Command error: Wrong command or parameter was sent to LS-1x0																				
<b>Notes:</b>																					

<b>Function name:</b> <b>Is100LMR</b>		<b>Library:</b> ls1x0cs100a.dll																			
<b>Function:</b> Light Mean Read from LS-1x0  This function returns the user calibration data memorized in LS-1x0																					
<b>Declaration:</b> Public Declare Function Is100LMR Lib "ls1x0cs100a.dll" (ByVal fNum As Integer, Unit as integer, LY As Double) As Long																					
<b>Parameter:</b>																					
<table><tr><th>Pass by:</th><th>Name:</th><th>Data type:</th><th>Data range:</th></tr><tr><td>ByVal</td><td>fNum</td><td>Integer</td><td></td></tr><tr><td>ByRef</td><td>Unit</td><td>Integer</td><td></td></tr><tr><td>ByRef</td><td>LY</td><td>Double</td><td></td></tr></table>				Pass by:	Name:	Data type:	Data range:	ByVal	fNum	Integer		ByRef	Unit	Integer		ByRef	LY	Double			
Pass by:	Name:	Data type:	Data range:																		
ByVal	fNum	Integer																			
ByRef	Unit	Integer																			
ByRef	LY	Double																			
<b>Parameter usage:</b>																					
<table><tr><th>Parameter:</th><th>Usage:</th></tr><tr><td>Fnum</td><td>Specify a file number, which was used to open this communication port.</td></tr><tr><td>Unit</td><td>Measurement unit (0 = cd/m<sup>2</sup> 1 = fL)</td></tr><tr><td>LY</td><td>Y User calibration data</td></tr></table>				Parameter:	Usage:	Fnum	Specify a file number, which was used to open this communication port.	Unit	Measurement unit (0 = cd/m <sup>2</sup> 1 = fL)	LY	Y User calibration data										
Parameter:	Usage:																				
Fnum	Specify a file number, which was used to open this communication port.																				
Unit	Measurement unit (0 = cd/m <sup>2</sup> 1 = fL)																				
LY	Y User calibration data																				
<b>Return type and value:</b>																					
<table><tr><th>Data</th><th>Explanation</th></tr><tr><td>Long</td><td>Use for Error-Checking</td></tr><tr><td>0</td><td>No error</td></tr><tr><td>-11</td><td>ER11: Memory value Error!</td></tr><tr><td>-20</td><td>ER20: EEPROM Error!</td></tr><tr><td>-30</td><td>ER30: Low battery!</td></tr><tr><td>-103</td><td>Time out: LS-1x0 didn't answer in proper time!</td></tr><tr><td>-104</td><td>Communication error: Please check for correct file number</td></tr><tr><td>-105</td><td>Command error: Wrong command or parameter was sent to LS-1x0</td></tr></table>				Data	Explanation	Long	Use for Error-Checking	0	No error	-11	ER11: Memory value Error!	-20	ER20: EEPROM Error!	-30	ER30: Low battery!	-103	Time out: LS-1x0 didn't answer in proper time!	-104	Communication error: Please check for correct file number	-105	Command error: Wrong command or parameter was sent to LS-1x0
Data	Explanation																				
Long	Use for Error-Checking																				
0	No error																				
-11	ER11: Memory value Error!																				
-20	ER20: EEPROM Error!																				
-30	ER30: Low battery!																				
-103	Time out: LS-1x0 didn't answer in proper time!																				
-104	Communication error: Please check for correct file number																				
-105	Command error: Wrong command or parameter was sent to LS-1x0																				
<b>Notes:</b>																					

<b>Function name:</b> <b>Is100LMW</b>		<b>Library:</b> ls1x0cs100a.dll																			
<b>Function:</b> Light Maean Write to LS-1x0  This function writes your user calibration data into LS-1x0 memory.																					
<b>Declaration:</b> Public Declare Function Is100LMW Lib "ls1x0cs100a.dll" (ByVal fNum As Integer, ByVal LY As Double) As Long																					
<b>Parameter:</b>																					
<table><tr><th>Pass by:</th><th>Name:</th><th>Data type:</th><th>Data range:</th></tr><tr><td>ByVal</td><td>fNum</td><td>Integer</td><td></td></tr><tr><td>ByRef</td><td>LY</td><td>Double</td><td></td></tr></table>				Pass by:	Name:	Data type:	Data range:	ByVal	fNum	Integer		ByRef	LY	Double							
Pass by:	Name:	Data type:	Data range:																		
ByVal	fNum	Integer																			
ByRef	LY	Double																			
<b>Parameter usage:</b>																					
<table><tr><th>Parameter:</th><th>Usage:</th></tr><tr><td>Fnum</td><td>Specify a file number, which was used to open this communication port.</td></tr><tr><td>LY</td><td>Y User calibration data</td></tr></table>				Parameter:	Usage:	Fnum	Specify a file number, which was used to open this communication port.	LY	Y User calibration data												
Parameter:	Usage:																				
Fnum	Specify a file number, which was used to open this communication port.																				
LY	Y User calibration data																				
<b>Return type and value:</b>																					
<table><tr><th>Data</th><th>Explanation</th></tr><tr><td>Long</td><td>Use for Error-Checking</td></tr><tr><td>0</td><td>No error</td></tr><tr><td>-11</td><td>ER11: Memory value Error!</td></tr><tr><td>-20</td><td>ER20: EEPROM Error!</td></tr><tr><td>-30</td><td>ER30: Low battery!</td></tr><tr><td>-103</td><td>Time out: LS-1x0 didn't answer in proper time!</td></tr><tr><td>-104</td><td>Communication error: Please check for correct file number</td></tr><tr><td>-105</td><td>Command error: Wrong command or parameter was sent to LS-1x0</td></tr></table>				Data	Explanation	Long	Use for Error-Checking	0	No error	-11	ER11: Memory value Error!	-20	ER20: EEPROM Error!	-30	ER30: Low battery!	-103	Time out: LS-1x0 didn't answer in proper time!	-104	Communication error: Please check for correct file number	-105	Command error: Wrong command or parameter was sent to LS-1x0
Data	Explanation																				
Long	Use for Error-Checking																				
0	No error																				
-11	ER11: Memory value Error!																				
-20	ER20: EEPROM Error!																				
-30	ER30: Low battery!																				
-103	Time out: LS-1x0 didn't answer in proper time!																				
-104	Communication error: Please check for correct file number																				
-105	Command error: Wrong command or parameter was sent to LS-1x0																				
<b>Notes:</b> <b>Please keep in mind that this user calibration data is in relation to the actual measurement data in LS-1x0. When performing user calibration, you first have to measure the light source in Minolta calibration mode and then you may send your corrected values!!</b>																					

<b>Function name:</b>		<b>Library:</b> 1x0cs100a.dll		
<b>Is100CCR</b>				
<b>Function:</b> Color Correction Read from LS-1x0				
<b>Declaration:</b> Public Declare Function Is100CCR Lib "ls1x0ls1x0cs100a.dll" (ByVal fNum As Integer, CCF As Double) As Long				
<b>Parameter:</b>				
<b>Pass by:</b>		<b>Name:</b>	<b>Data type:</b>	<b>Data range:</b>
ByVal		fNum	Integer	
ByRef		CCF	Double	0.002 to 9.998
<b>Parameter usage:</b>				
<b>Parameter:</b>		<b>Usage:</b>		
fNum		Specify a file number, which was used to open this communication port.		
CCF		Variable used to return the CCF data of LS-1x0		
<b>Return type and value:</b>				
<b>Data</b>		<b>Explanation</b>		
Long		Use for Error-Checking		
0		No error		
-11		ER11: Memory value Error!		
-20		ER20: EEPROM Error!		
-30		ER30: Low battery!		
-103		Time out: LS-1x0 didn't answer in proper time!		
-104		Communication error: Please check for correct file number		
-105		Command error: Wrong command or parameter was sent to LS-1x0		
<b>Notes:</b>				

<b>Function name:</b> <b>Is100CCW</b>		<b>Library:</b> 1x0cs100a.dll																			
<b>Function:</b> Color Correction Write to LS-1x0																					
<b>Declaration:</b> Public Declare Function Is100CCW Lib "Is1x0Is1x0cs100a.dll" (ByVal fNum As Integer, CCF As Double) As Long																					
<b>Parameter:</b>																					
<table><tr><th>Pass by:</th><th>Name:</th><th>Data type:</th><th>Data range:</th></tr><tr><td>ByVal</td><td>fNum</td><td>Integer</td><td></td></tr><tr><td>ByRef</td><td>CCF</td><td>Double</td><td></td></tr></table>		Pass by:	Name:	Data type:	Data range:	ByVal	fNum	Integer		ByRef	CCF	Double									
Pass by:	Name:	Data type:	Data range:																		
ByVal	fNum	Integer																			
ByRef	CCF	Double																			
<b>Parameter usage:</b>																					
<table><tr><th>Parameter:</th><th>Usage:</th></tr><tr><td>fNum</td><td>Specify a file number, which was used to open this communication port.</td></tr><tr><td>CCF</td><td>Variable used to send the CCF data to LS-1x0</td></tr></table>		Parameter:	Usage:	fNum	Specify a file number, which was used to open this communication port.	CCF	Variable used to send the CCF data to LS-1x0														
Parameter:	Usage:																				
fNum	Specify a file number, which was used to open this communication port.																				
CCF	Variable used to send the CCF data to LS-1x0																				
<b>Return type and value:</b>																					
<table><tr><th>Data</th><th>Explanation</th></tr><tr><td>Long</td><td>Use for Error-Checking</td></tr><tr><td>0</td><td>No error</td></tr><tr><td>-11</td><td>ER11: Memory value Error!</td></tr><tr><td>-20</td><td>ER20: EEPROM Error!</td></tr><tr><td>-30</td><td>ER30: Low battery!</td></tr><tr><td>-103</td><td>Time out: LS-1x0 didn't answer in proper time!</td></tr><tr><td>-104</td><td>Communication error: Please check for correct file number</td></tr><tr><td>-105</td><td>Command error: Wrong command or parameter was sent to LS-1x0</td></tr></table>		Data	Explanation	Long	Use for Error-Checking	0	No error	-11	ER11: Memory value Error!	-20	ER20: EEPROM Error!	-30	ER30: Low battery!	-103	Time out: LS-1x0 didn't answer in proper time!	-104	Communication error: Please check for correct file number	-105	Command error: Wrong command or parameter was sent to LS-1x0		
Data	Explanation																				
Long	Use for Error-Checking																				
0	No error																				
-11	ER11: Memory value Error!																				
-20	ER20: EEPROM Error!																				
-30	ER30: Low battery!																				
-103	Time out: LS-1x0 didn't answer in proper time!																				
-104	Communication error: Please check for correct file number																				
-105	Command error: Wrong command or parameter was sent to LS-1x0																				
<b>Notes:</b>																					

## **Colorimetric support functions**

The following is a collection of some colorimetric calculation functions. Of course for LS-100 or LS-110 these are not required!

<b>Function name:</b> <b>YxyToXYZ</b>		<b>Library:</b> ls1x0cs100a.dll																													
<b>Function:</b> Calculates Yxy to XYZ values																															
<b>Declaration:</b> Public Declare Function YxyToXYZ Lib "ls1x0cs100a.dll" (ByVal LY As Double, ByVal sx As Double, ByVal sy As Double, X As Double, Y As Double, Z As Double) As Long																															
<b>Parameter:</b>																															
<table><tr><th>Pass by:</th><th>Name:</th><th>Data type:</th><th>Data range:</th></tr><tr><td>ByVal</td><td>LY</td><td>Double</td><td></td></tr><tr><td>ByVal</td><td>sx</td><td>Double</td><td></td></tr><tr><td>ByVal</td><td>sy</td><td>Double</td><td></td></tr><tr><td>ByRef</td><td>X</td><td>Double</td><td></td></tr><tr><td>ByRef</td><td>Y</td><td>Double</td><td></td></tr><tr><td>ByRef</td><td>Z</td><td>Double</td><td></td></tr></table>				Pass by:	Name:	Data type:	Data range:	ByVal	LY	Double		ByVal	sx	Double		ByVal	sy	Double		ByRef	X	Double		ByRef	Y	Double		ByRef	Z	Double	
Pass by:	Name:	Data type:	Data range:																												
ByVal	LY	Double																													
ByVal	sx	Double																													
ByVal	sy	Double																													
ByRef	X	Double																													
ByRef	Y	Double																													
ByRef	Z	Double																													
<b>Parameter usage:</b>																															
<table><tr><th>Parameter:</th><th>Usage:</th></tr><tr><td>LY</td><td>Y value sent to function</td></tr><tr><td>Sx</td><td>x value sent to function</td></tr><tr><td>Sy</td><td>y value sent to function</td></tr><tr><td>X</td><td>X value returned from function</td></tr><tr><td>Y</td><td>Y value returned from function</td></tr><tr><td>Z</td><td>Z value returned from function</td></tr></table>				Parameter:	Usage:	LY	Y value sent to function	Sx	x value sent to function	Sy	y value sent to function	X	X value returned from function	Y	Y value returned from function	Z	Z value returned from function														
Parameter:	Usage:																														
LY	Y value sent to function																														
Sx	x value sent to function																														
Sy	y value sent to function																														
X	X value returned from function																														
Y	Y value returned from function																														
Z	Z value returned from function																														
<b>Return type and value:</b>																															
<table><tr><th>Data</th><th>Explanation</th></tr><tr><td>Long</td><td>Use for Error-Checking</td></tr><tr><td>0</td><td>No error</td></tr><tr><td>-90</td><td>Calculation Error: Values passed to the function could not be calculated!</td></tr></table>				Data	Explanation	Long	Use for Error-Checking	0	No error	-90	Calculation Error: Values passed to the function could not be calculated!																				
Data	Explanation																														
Long	Use for Error-Checking																														
0	No error																														
-90	Calculation Error: Values passed to the function could not be calculated!																														
<b>Notes:</b>																															

<b>Function name:</b> <b>xyToDomWL</b>		<b>Library:</b> ls1x0cs100a.dll																					
<b>Function:</b> Calculates dominant wavelength and excitation purity based on xy values																							
<b>Declaration:</b> Public Declare Function xyToDomWL Lib "ls1x0cs100a.dll" (ByVal x As Double, ByVal y As Double, WLd As Double, Pe As Double) As Long																							
<b>Parameter:</b>																							
<table><tr><th>Pass by:</th><th>Name:</th><th>Data type:</th><th>Data range:</th></tr><tr><td>ByVal</td><td>x</td><td>Double</td><td></td></tr><tr><td>ByVal</td><td>y</td><td>Double</td><td></td></tr><tr><td>ByRef</td><td>WLd</td><td>Double</td><td></td></tr><tr><td>ByRef</td><td>Pe</td><td>Double</td><td></td></tr></table>		Pass by:	Name:	Data type:	Data range:	ByVal	x	Double		ByVal	y	Double		ByRef	WLd	Double		ByRef	Pe	Double			
Pass by:	Name:	Data type:	Data range:																				
ByVal	x	Double																					
ByVal	y	Double																					
ByRef	WLd	Double																					
ByRef	Pe	Double																					
<b>Parameter usage:</b>																							
<table><tr><th>Parameter:</th><th>Usage:</th></tr><tr><td>x</td><td>x value sent to function</td></tr><tr><td>y</td><td>y value sent to function</td></tr><tr><td>u</td><td>Dominant wavelength value returned from function</td></tr><tr><td>v</td><td>Excitation purity value returned from function</td></tr></table>		Parameter:	Usage:	x	x value sent to function	y	y value sent to function	u	Dominant wavelength value returned from function	v	Excitation purity value returned from function												
Parameter:	Usage:																						
x	x value sent to function																						
y	y value sent to function																						
u	Dominant wavelength value returned from function																						
v	Excitation purity value returned from function																						
<b>Return type and value:</b>																							
<table><tr><th>Data</th><th>Explanation</th></tr><tr><td>Long</td><td>Use for Error-Checking</td></tr><tr><td>0</td><td>No error</td></tr><tr><td>-90</td><td>Calculation Error: Values passed to the function could not be calculated!</td></tr></table>		Data	Explanation	Long	Use for Error-Checking	0	No error	-90	Calculation Error: Values passed to the function could not be calculated!														
Data	Explanation																						
Long	Use for Error-Checking																						
0	No error																						
-90	Calculation Error: Values passed to the function could not be calculated!																						
<b>Notes:</b>																							



<b>Function name:</b> <b>xyTouv</b>		<b>Library:</b> ls1x0cs100a.dll		
<b>Function:</b> Calculates xy to uv values				
<b>Declaration:</b> Public Declare Function xyTouv Lib "ls1x0cs100a.dll" (ByVal x As Double, ByVal y As Double, u As Double, v As Double) As Long				
<b>Parameter:</b>				
<b>Pass by:</b>		<b>Name:</b>	<b>Data type:</b>	<b>Data range:</b>
ByVal		x	Double	
ByVal		y	Double	
ByRef		u	Double	
ByRef		v	Double	
<b>Parameter usage:</b>				
<b>Parameter:</b>		<b>Usage:</b>		
x		x value sent to function		
y		y value sent to function		
u		u value returned from function		
v		v value returned from function		
<b>Return type and value:</b>				
<b>Data</b>		<b>Explanation</b>		
Long		Use for Error-Checking		
0		No error		
-90		Calculation Error: Values passed to the function could not be calculated!		
<b>Notes:</b>				

<b>Function name:</b> <b>xyToudvd</b>		<b>Library:</b> ls1x0cs100a.dll																					
<b>Function:</b> Calculates xy to u'v' values																							
<b>Declaration:</b> Public Declare Function xyToudvd Lib "ls1x0cs100a.dll" (ByVal x As Double, ByVal y As Double, ud As Double, vd As Double) As Long																							
<b>Parameter:</b>																							
<table><tr><th>Pass by:</th><th>Name:</th><th>Data type:</th><th>Data range:</th></tr><tr><td>ByVal</td><td>x</td><td>Double</td><td></td></tr><tr><td>ByVal</td><td>y</td><td>Double</td><td></td></tr><tr><td>ByRef</td><td>ud</td><td>Double</td><td></td></tr><tr><td>ByRef</td><td>vd</td><td>Double</td><td></td></tr></table>		Pass by:	Name:	Data type:	Data range:	ByVal	x	Double		ByVal	y	Double		ByRef	ud	Double		ByRef	vd	Double			
Pass by:	Name:	Data type:	Data range:																				
ByVal	x	Double																					
ByVal	y	Double																					
ByRef	ud	Double																					
ByRef	vd	Double																					
<b>Parameter usage:</b>																							
<table><tr><th>Parameter:</th><th>Usage:</th></tr><tr><td>x</td><td>x value sent to function</td></tr><tr><td>y</td><td>y value sent to function</td></tr><tr><td>ud</td><td>u' value returned from function</td></tr><tr><td>vd</td><td>v' value returned from function</td></tr></table>		Parameter:	Usage:	x	x value sent to function	y	y value sent to function	ud	u' value returned from function	vd	v' value returned from function												
Parameter:	Usage:																						
x	x value sent to function																						
y	y value sent to function																						
ud	u' value returned from function																						
vd	v' value returned from function																						
<b>Return type and value:</b>																							
<table><tr><th>Data</th><th>Explanation</th></tr><tr><td>Long</td><td>Use for Error-Checking</td></tr><tr><td>0</td><td>No error</td></tr><tr><td>-90</td><td>Calculation Error: Values passed to the function could not be calculated!</td></tr></table>		Data	Explanation	Long	Use for Error-Checking	0	No error	-90	Calculation Error: Values passed to the function could not be calculated!														
Data	Explanation																						
Long	Use for Error-Checking																						
0	No error																						
-90	Calculation Error: Values passed to the function could not be calculated!																						
<b>Notes:</b>																							

<b>Function name:</b> <b>xyToRGBLong</b>		<b>Library:</b> ls1x0cs100a.dll													
<b>Function:</b> Calculates xy to a long RGB value  RGB value is compatible to VB color property															
<b>Declaration:</b> Public Declare Function xyToRGBLong Lib "ls1x0cs100a.dll" (ByVal x As Double, ByVal y As Double) As Long															
<b>Parameter:</b> <table><tr><th>Pass by:</th><th>Name:</th><th>Data type:</th><th>Data range:</th></tr><tr><td>ByVal</td><td>x</td><td>Double</td><td></td></tr><tr><td>ByVal</td><td>y</td><td>Double</td><td></td></tr></table>				Pass by:	Name:	Data type:	Data range:	ByVal	x	Double		ByVal	y	Double	
Pass by:	Name:	Data type:	Data range:												
ByVal	x	Double													
ByVal	y	Double													
<b>Parameter usage:</b> <table><tr><th>Parameter:</th><th>Usage:</th></tr><tr><td>x</td><td>x value sent to function</td></tr><tr><td>y</td><td>y value sent to function</td></tr></table>				Parameter:	Usage:	x	x value sent to function	y	y value sent to function						
Parameter:	Usage:														
x	x value sent to function														
y	y value sent to function														
<b>Return type and value:</b> <table><tr><th>Data</th><th>Explanation</th></tr><tr><td>Long</td><td>Use for Error-Checking</td></tr><tr><td>0 - FFFFFFFF</td><td>RGB long color value</td></tr><tr><td>-90</td><td>Calculation Error: Values passed to the function could not be calculated!</td></tr></table>				Data	Explanation	Long	Use for Error-Checking	0 - FFFFFFFF	RGB long color value	-90	Calculation Error: Values passed to the function could not be calculated!				
Data	Explanation														
Long	Use for Error-Checking														
0 - FFFFFFFF	RGB long color value														
-90	Calculation Error: Values passed to the function could not be calculated!														
<b>Notes:</b>															

<b>Function name:</b> <b>XYZTouv</b>		<b>Library:</b> ls1x0cs100a.dll																									
<b>Function:</b> Calculates XYZ to uv values																											
<b>Declaration:</b> Public Declare Function XYZTouv Lib "ls1x0cs100a.dll" (ByVal X As Double, ByVal Y As Double, ByVal Z As Double, u As Double, v As Double) As Long																											
<b>Parameter:</b>																											
<table><tr><th>Pass by:</th><th>Name:</th><th>Data type:</th><th>Data range:</th></tr><tr><td>ByVal</td><td>X</td><td>Double</td><td></td></tr><tr><td>ByVal</td><td>Y</td><td>Double</td><td></td></tr><tr><td>ByVal</td><td>Z</td><td>Double</td><td></td></tr><tr><td>ByRef</td><td>u</td><td>Double</td><td></td></tr><tr><td>ByRef</td><td>v</td><td>Double</td><td></td></tr></table>		Pass by:	Name:	Data type:	Data range:	ByVal	X	Double		ByVal	Y	Double		ByVal	Z	Double		ByRef	u	Double		ByRef	v	Double			
Pass by:	Name:	Data type:	Data range:																								
ByVal	X	Double																									
ByVal	Y	Double																									
ByVal	Z	Double																									
ByRef	u	Double																									
ByRef	v	Double																									
<b>Parameter usage:</b>																											
<table><tr><th>Parameter:</th><th>Usage:</th></tr><tr><td>X</td><td>X value sent to function</td></tr><tr><td>Y</td><td>Y value sent to function</td></tr><tr><td>Z</td><td>Z value sent to function</td></tr><tr><td>u</td><td>u value returned from function</td></tr><tr><td>v</td><td>v value returned from function</td></tr></table>		Parameter:	Usage:	X	X value sent to function	Y	Y value sent to function	Z	Z value sent to function	u	u value returned from function	v	v value returned from function														
Parameter:	Usage:																										
X	X value sent to function																										
Y	Y value sent to function																										
Z	Z value sent to function																										
u	u value returned from function																										
v	v value returned from function																										
<b>Return type and value:</b>																											
<table><tr><th>Data</th><th>Explanation</th></tr><tr><td>Long</td><td>Use for Error-Checking</td></tr><tr><td>0</td><td>No error</td></tr><tr><td>-90</td><td>Calculation Error: Values passed to the function could not be calculated!</td></tr></table>		Data	Explanation	Long	Use for Error-Checking	0	No error	-90	Calculation Error: Values passed to the function could not be calculated!																		
Data	Explanation																										
Long	Use for Error-Checking																										
0	No error																										
-90	Calculation Error: Values passed to the function could not be calculated!																										
<b>Notes:</b>																											

<b>Function name:</b> <b>XYZToudvd</b>		<b>Library:</b> ls1x0cs100a.dll																									
<b>Function:</b> Calculates XYZ to u’v’ values																											
<b>Declaration:</b> Public Declare Function XYZToudvd Lib "ls1x0cs100a.dll" (ByVal X As Double, ByVal Y As Double, ByVal Z As Double, ud As Double, vd As Double) As Long																											
<b>Parameter:</b>																											
<table><tr><th>Pass by:</th><th>Name:</th><th>Data type:</th><th>Data range:</th></tr><tr><td>ByVal</td><td>X</td><td>Double</td><td></td></tr><tr><td>ByVal</td><td>Y</td><td>Double</td><td></td></tr><tr><td>ByVal</td><td>Z</td><td>Double</td><td></td></tr><tr><td>ByRef</td><td>ud</td><td>Double</td><td></td></tr><tr><td>ByRef</td><td>vd</td><td>Double</td><td></td></tr></table>				Pass by:	Name:	Data type:	Data range:	ByVal	X	Double		ByVal	Y	Double		ByVal	Z	Double		ByRef	ud	Double		ByRef	vd	Double	
Pass by:	Name:	Data type:	Data range:																								
ByVal	X	Double																									
ByVal	Y	Double																									
ByVal	Z	Double																									
ByRef	ud	Double																									
ByRef	vd	Double																									
<b>Parameter usage:</b>																											
<table><tr><th>Parameter:</th><th>Usage:</th></tr><tr><td>X</td><td>X value sent to function</td></tr><tr><td>Y</td><td>Y value sent to function</td></tr><tr><td>Z</td><td>Z value sent to function</td></tr><tr><td>ud</td><td>u’ value returned from function</td></tr><tr><td>vd</td><td>v’ value returned from function</td></tr></table>				Parameter:	Usage:	X	X value sent to function	Y	Y value sent to function	Z	Z value sent to function	ud	u’ value returned from function	vd	v’ value returned from function												
Parameter:	Usage:																										
X	X value sent to function																										
Y	Y value sent to function																										
Z	Z value sent to function																										
ud	u’ value returned from function																										
vd	v’ value returned from function																										
<b>Return type and value:</b>																											
<table><tr><th>Data</th><th>Explanation</th></tr><tr><td>Long</td><td>Use for Error-Checking</td></tr><tr><td>0</td><td>No error</td></tr><tr><td>-90</td><td>Calculation Error: Values passed to the function could not be calculated!</td></tr></table>				Data	Explanation	Long	Use for Error-Checking	0	No error	-90	Calculation Error: Values passed to the function could not be calculated!																
Data	Explanation																										
Long	Use for Error-Checking																										
0	No error																										
-90	Calculation Error: Values passed to the function could not be calculated!																										
<b>Notes:</b>																											

<b>Function name:</b> <b>XYZToRGBLong</b>		<b>Library:</b> ls1x0cs100a.dll																	
<b>Function:</b> Calculates XYZ to a long RGB value  RGB value is compatible to VB color property																			
<b>Declaration:</b> Public Declare Function XYZToRGBLong Lib "ls1x0cs100a.dll" (ByVal X As Double, ByVal Y As Double, ByVal Z As Double) As Long																			
<b>Parameter:</b>																			
<table><tr><th>Pass by:</th><th>Name:</th><th>Data type:</th><th>Data range:</th></tr><tr><td>ByVal</td><td>X</td><td>Double</td><td></td></tr><tr><td>ByVal</td><td>Y</td><td>Double</td><td></td></tr><tr><td>ByVal</td><td>Z</td><td>Double</td><td></td></tr></table>				Pass by:	Name:	Data type:	Data range:	ByVal	X	Double		ByVal	Y	Double		ByVal	Z	Double	
Pass by:	Name:	Data type:	Data range:																
ByVal	X	Double																	
ByVal	Y	Double																	
ByVal	Z	Double																	
<b>Parameter usage:</b>																			
<table><tr><th>Parameter:</th><th>Usage:</th></tr><tr><td>X</td><td>X value sent to function</td></tr><tr><td>Y</td><td>Y value sent to function</td></tr><tr><td>Z</td><td>Z value sent to function</td></tr></table>				Parameter:	Usage:	X	X value sent to function	Y	Y value sent to function	Z	Z value sent to function								
Parameter:	Usage:																		
X	X value sent to function																		
Y	Y value sent to function																		
Z	Z value sent to function																		
<b>Return type and value:</b>																			
<table><tr><th>Data</th><th>Explanation</th></tr><tr><td>Long</td><td>Use for Error-Checking</td></tr><tr><td>0 - FFFFFFFF</td><td>RGB long color value</td></tr><tr><td>-90</td><td>Calculation Error: Values passed to the function could not be calculated!</td></tr></table>				Data	Explanation	Long	Use for Error-Checking	0 - FFFFFFFF	RGB long color value	-90	Calculation Error: Values passed to the function could not be calculated!								
Data	Explanation																		
Long	Use for Error-Checking																		
0 - FFFFFFFF	RGB long color value																		
-90	Calculation Error: Values passed to the function could not be calculated!																		
<b>Notes:</b>																			

<b>Function name:</b>  uvToTduv		<b>Library:</b> ls1x0cs100a.dll																				
<b>Function:</b> Calculates uv to Tduv (Correlated Color Temperature and delta uv) values																						
<b>Declaration:</b> Public Declare Function uvToTduv Lib "ls1x0cs100a.dll" (ByVal u As Double, ByVal v As Double, T As Double, duv As Double) As Long																						
<b>Parameter:</b>																						
	<table><tr><th>Pass by:</th><th>Name:</th><th>Data type:</th><th>Data range:</th></tr><tr><td>ByVal</td><td>u</td><td>Double</td><td></td></tr><tr><td>ByVal</td><td>v</td><td>Double</td><td></td></tr><tr><td>ByRef</td><td>T</td><td>Double</td><td></td></tr><tr><td>ByRef</td><td>duv</td><td>Double</td><td></td></tr></table>	Pass by:	Name:	Data type:	Data range:	ByVal	u	Double		ByVal	v	Double		ByRef	T	Double		ByRef	duv	Double		
Pass by:	Name:	Data type:	Data range:																			
ByVal	u	Double																				
ByVal	v	Double																				
ByRef	T	Double																				
ByRef	duv	Double																				
<b>Parameter usage:</b>																						
	<table><tr><th>Parameter:</th><th>Usage:</th></tr><tr><td>u</td><td>x value sent to function</td></tr><tr><td>v</td><td>y value sent to function</td></tr><tr><td>T</td><td>T value returned from function</td></tr><tr><td>duv</td><td>duv value returned from function</td></tr></table>	Parameter:	Usage:	u	x value sent to function	v	y value sent to function	T	T value returned from function	duv	duv value returned from function											
Parameter:	Usage:																					
u	x value sent to function																					
v	y value sent to function																					
T	T value returned from function																					
duv	duv value returned from function																					
<b>Return type and value:</b>																						
	<table><tr><th>Data</th><th>Explanation</th></tr><tr><td>Long</td><td>Use for Error-Checking</td></tr><tr><td>0</td><td>No error</td></tr><tr><td>-90</td><td>Calculation Error: Values passed to the function could not be calculated!</td></tr><tr><td>-92</td><td>Out of range, color temperature could not be calculated!</td></tr></table>	Data	Explanation	Long	Use for Error-Checking	0	No error	-90	Calculation Error: Values passed to the function could not be calculated!	-92	Out of range, color temperature could not be calculated!											
Data	Explanation																					
Long	Use for Error-Checking																					
0	No error																					
-90	Calculation Error: Values passed to the function could not be calculated!																					
-92	Out of range, color temperature could not be calculated!																					
<b>Notes:</b>																						

<b>Function name:</b>		<b>Library:</b> ls1x0cs100a.dll		
<b>RGBLongToRGB</b>				
<b>Function:</b> Calculates RGB long variable to separate R,G and B values				
<b>Declaration:</b> Public Declare Function RGBLongToRGB Lib "ls1x0cs100a.dll" (ByVal RGBLong As Long, R As Long, G As Long, B As Long) As Long				
<b>Parameter:</b>				
<b>Pass by:</b>		<b>Name:</b>	<b>Data type:</b>	<b>Data range:</b>
ByVal		RGBLong	Long	
ByRef		R	Long	
ByRef		G	Long	
ByRef		B	Long	
<b>Parameter usage:</b>				
<b>Parameter:</b>		<b>Usage:</b>		
RGBLong		RGB long value sent to function		
R		R value returned from function		
G		G value returned from function		
B		B value returned from function		
<b>Return type and value:</b>				
<b>Data</b>		<b>Explanation</b>		
Long		Use for Error-Checking		
0		No error		
-90		Calculation Error: Values passed to the function could not be calculated!		
-91		RGB Long values can't be negative!		
<b>Notes:</b>				



## **Include modules for VBA & VB**

These “modules” are made to provide all function declare statements. In addition, they provide a routine for converting error numbers to text. For customizing the error messages to any local language, simply edit the text in the “ErrNoToText” function.

### ***VBA Visual Basic for Applications***

The package includes the “CS100aDLL\_VBAInclude.bas” & “LS1x0DLL\_VBAInclude.bas” file. These files simply can be imported to any software, which is supporting Visual Basic for Applications.

In EXCEL for example, simply start the source code editor and select “Import File” from File menu.

**Note!**

In the examples for EXCEL this is of course already done and thus not necessary. If using the example file as a starting point for own files, also all functions are already implemented.

### ***VB Visual Basic***

The package includes the “CS100aDLL\_VBInclude.bas” & “LS1x0DLL\_VBInclude.bas” file. These files simply can be imported to any project of Visual Basic and will provide all function declare statements as well as some error checking code.

**Note!**

All Visual Basic versions are supported, however as the DLL is using the Windows API, only 32 bit versions of Windows are supported!


## CS-100A Examples by using Microsoft EXCEL

The ls1x0cs100a.dll comes together with two example files by using Microsoft EXCEL. One shows the usage for CS-100A and is explained here. The other one is for LS100 and LS110 and is explained later in this document.

CS-100a\_Demo.XLS contains seven sheets with different samples. In addition there is a hidden sheet, which supplies the basic data for the CIE color diagrams.

### Yxy measurement and graphical display

This example shows how Yxy data can be read from CS-100A and displayed in a colored xy diagram. In addition, it shows calculation of XYZ, uv, u'v' and correlated color temperature.



How to use:


1. Select the COM port, to which you connected the CS-100A, by the drop down list
2. Push <Open Port>  
CS-100A will be automatically switched to absolute measurement mode  
User or Minolta calibration mode setting will not be changed  
Fast or slow mode setting will not be changed
3. Now you simply can push <Measure> to get the measurement data of CS-100A
4. Finally push <Close>

#### Note!

- When opening COM port, the previous measurement data will be deleted
- If you don't close the COM port before changing to another sheet, the COM port will be closed automatically.

## Yxy measurement and uv (u'v') graphical display

This example shows how Yxy data can be read from CS-100A and uv (u'v') values can be displayed in a colored uv (u'v') diagram. In addition, it shows calculation of XYZ, uv, u'v' and correlated color temperature. Basic functionality is same like the Yxy sheet, only difference is the uv diagramm



How to use:


1. Select the COM port, to which you connected the CS-100A, by the drop down list
2. Push <Open Port>  
CS-100A will be automatically switched to absolute measurement mode  
User or Minolta calibration mode setting will not be changed  
Fast or slow mode setting will not be changed
3. Now you simply can push <Measure> to get the measurement data of CS-100A
4. Finally push <Close>

### Note!

- When opening COM port, the previous measurement data will be deleted
- If you don't close the COM port before changing to another sheet, the COM port will be closed automatically.

## Yxy multi measurement and graphical display

This example shows how Yxy data can be read from CS-100A and multiple data can be displayed in a colored xy diagram. In addition, it shows calculation of XYZ, uv, u'v' and correlated color temperature.



How to use:

1. Select the COM port, to which you connected the CS-100A, by the drop down list
2. Push <Open Port>  
CS-100A will be automatically switched to absolute measurement mode  
User or Minolta calibration mode setting will not be changed  
Fast or slow mode setting will not be changed
3. Now you simply can push <Measure> to get the measurement data of CS-100A
4. The list can contain up to 10 sets of measurement data and will then start from the beginning
5. Finally push <Close>

### Note!


- When opening COM port, the previous measurement data will be deleted
- If you don't close the COM port before changing to another sheet, the COM port will be closed automatically.

- When opening COM port, the previous measurement data will be deleted
- If you don't close the COM port before changing to another sheet, the COM port will be closed automatically.

## Sequence of difference measurements

This example shows how Yxy measurement sequence can be read from CS-100A and displayed in three trend diagrams. In addition, it shows calculation of XYZ, uv, u'v' and correlated color temperature.

Difference to previous one is that CS-100A is working in difference mode.



How to use:

1. Select the COM port, to which you connected the CS-100A, by the drop down list
2. Push <Open Port>  
CS-100A will be automatically switched to difference measurement mode  
User or Minolta calibration mode setting will not be changed  
Fast or slow mode setting will not be changed
3. Specify interval time and number of measurements
4. Push <Interval Measure> to start your sequence
5. Finally push <Close>

### Note!

- To set up your target for this difference measurement please refer to “Tools” sheet
- When opening COM port, the previous measurement data will be deleted
- If you don't close the COM port before changing to another sheet, the COM port will be closed automatically.

## Tools

This example is made to show how settings can be changed, how target functions can be used and how user calibration can be used!

The screenshot displays the CS-100A software interface with a yellow background. It features a 'COM Port' dropdown menu set to 'COM 1', a 'Measure' button, and a 'Clear memory' button. A central display shows measurement data for Y, x, and y axes. Below this, there are buttons for 'FAST', 'SLOW', 'ABS', 'DIFF', 'PRESET', and 'VARI'. Further down, there are 'Open Port' and 'Close Port' buttons. At the bottom, there are 'Read Target', 'Write Target', 'Read VARI', and 'Write VARI' buttons. The interface also includes a 'Meas -> Target' button and a 'Copyright 2002, Minolta Europe GmbH U. Strahlendorf' notice.

Axis	Value
Y	67,32
x	0,3422
y	0,3574

Axis	Value
Y	77,59
x	0,3160
y	0,3291

Axis	Value
Y	85
x	0,3000
y	0,3200

How to use:

1. Select the COM port, to which you connected the CS-100A, by the drop down list
2. Push <Open Port>
  - CS-100A will be automatically switched to absolute measurement mode
  - CS-100A will automatically be switched to Fast mode
  - CS-100A will automatically be switched to Minolta calibration mode
3. The different modes simply can be change by pushing to the relevant button.
4. You can read or write target data to CS-100A
  - Push <Read Target> to get the data from CS-100A
  - Change your target data
  - Push <Write Target> to CS-100A
5. If you want to set the actual measurement data as target, your first have to measure
  - Push <Measure> (Data with warning for out of range will not be accepted)
  - <Meas. -> Target> button will be enabled
  - Push <Meas. -> Target> button to store measurement data into CS-100A target channel.

6. You can read user calibration standard data

Push <Read VARI> to get the data from CS-100A

7. To memorize new user calibration data, you first have to measure.

Measure your standard light source

Enter your own standard data into the user calibration fields

Push <Write VARI> to send the data to CS-100A

**Note!**

**User calibration is performed by calculating a factor against original measurement data, thus you cannot perform user calibration without first measuring the standard.**

8. By pushing the <Clear> button you can delete the memory in CS-100A

9. Finally push <Close>

**Note!**

- When opening COM port, the previous measurement data will be deleted
- If you don't close the COM port before changing to another sheet, the COM port will be closed automatically.




## LS-1x0 Examples by using Microsoft EXCEL

This section is explaining about the usage of the second example with Microsoft EXCEL, which is used for LS-100 and LS-110!

LS-1x0\_Demo.XLS contains four sheets with different samples.

### Sequence measurement and graphical display

This example shows how measurement sequence can be read from LS-100/-110 and displayed in a list. In addition, it shows graphical display of the sequence.



How to use:

1. Select the COM port, to which you connected the LS-100/-110, by the drop down list
2. Push <Open Port>  
LS-1x0 will be automatically switched to absolute measurement mode  
User or Minolta calibration mode setting will not be changed  
Fast or slow mode setting will not be changed
3. For single measurement proceed as follows:  
Select the cell "C" within the row where you would like the measurement data to go.  
Push <1 time Measure> to get the measurement data of LS-1x0
4. In addition you could start a sequence measurement.  
Specify interval time and number of measurements  
Select the cell "C" within the row where you would like the first measurement data to go.  
Push <Interval Measure> to start your sequence
5. Finally push <Close>


#### Note!

- When opening COM port, the previous measurement data will be deleted
- If you don't close the COM port before changing to another sheet, the COM port will be closed automatically.

## Sequence of difference measurements

This example shows how measurement sequence can be read from LS-100/-110 and displayed in a trend diagrams.

Difference to previous one is that LS-1x0 is working in difference mode.



How to use:

1. Select the COM port, to which you connected the LS-100/-110, by the drop down list
2. Push <Open Port>  
LS-1x0 will be automatically switched to difference measurement mode  
User or Minolta calibration mode setting will not be changed  
Fast or slow mode setting will not be changed
3. Specify interval time and number of measurements
4. Push <Interval Measure> to start your sequence
5. Finally push <Close>

### Note!

- To set up your target for this difference measurement please refer to “Tools” sheet
- When opening COM port, the previous measurement data will be deleted
- If you don't close the COM port before changing to another sheet, the COM port will be closed automatically.

## Tools

This example is made to show how settings can be changed, how target functions can be used and how user calibration can be used!

The screenshot shows a software interface for the LS-100/-110 device. It features a yellow background with orange buttons and text. The interface is organized into several sections:

- COM Port:** A dropdown menu showing "COM 1".
- Buttons:** "Open Port", "Close Port", "Clear memory", "Measure", "Meas -> Target", "Read Target", "Write Target", "Read CCF", "Write CCF", "Read LUMI", "Write LUMI".
- Mode Selection:** A vertical stack of buttons: "FAST", "SLOW", "ABS", "DIFF", "PRESET", "VARI / CCF", "VARI / LUMI", "VARI / CCF / LUMI", "Continuous", "Peak".
- Display:** Shows "Y 13,3 cd/m²" and "CCF 1,000". Below this, "Y 0 cd/m²" and "0 cd/m²" are displayed.
- Dropdowns:** "CIE Standard Illuminant A" is selected in a dropdown menu.

Copyright 2003, Minolta Europe GmbH U.Strahlendorf

How to use:

1. Select the COM port, to which you connected the LS-100/-110, by the drop down list
2. Push <Open Port>  
LS-1x0 will be automatically switched to Fast mode  
Absolute, difference, calibration and Peak mode settings will be detected automatically
3. The different modes simply can be change by pushing to the relevant button.
4. You can read or write target data to LS-1x0  
Push <Read Target> to get the data from LS-1x0  
Change your target data  
Push <Write Target> to LS-1x0
5. If you want to set the actual measurement data as target, your first have to measure  
Push <Measure> (Data with warning for out of range will not be accepted)  
Push <Meas. -> Target> button to store measurement data into LS-1x0 target channel.

6. You can read user calibration (Luminance) standard data  
Push <Read LUMI> to get the data from LS-1x0
7. To memorize new user calibration data, you first have to measure.  
Measure your standard light source  
Enter your own standard data into the user calibration field  
Push <Write LUMI> to send the data to LS-1x0

**Note!**

**User calibration is performed by calculating a factor against original measurement data, thus you cannot perform user calibration without first measuring the standard.**

8. You can read CCF (Color Correction Factors)  
Push <Read CCF> to get the data from LS-1x0
9. To memorize new CCF data, follow this procedure  
Enter your own CCF (0.002 to 9.998) data into the CCF field  
Push <Write CCF> to send the data to LS-1x0
10. By the drop down list, you can select pre defined CCF factors. Please refer to the next page for details about how to define CCF factors. If reading CCF factor from instrument and this factor is defined, the defined name will be shown in the list. If value is multiple times in the definition, the first appearance will be selected!
11. By pushing the <Clear> button you can delete the memory is LS-1x0
11. Finally push <Close>

**Note!**

- If you don't close the COM port before changing to another sheet, the COM port will be closed automatically.

## CCF definition

On this sheet you can define own CCF factors:

	A	B	C	D	E
1		Name	Value	Number of CCF factors	19
2	0	CIE Standard Illuminant A	1,000		
3	1	CIE Standard Illuminant B	1,007		
4	2	CIE Standard Illuminant C	1,010		
5	3	CIE Standard Illuminant D65	1,011		
6	4	Daylight flourescent lamp (F5)	1,013		
7	5	White flourescent lamp (F6)	1,008		
8	6	Three-band flourescent lamp	1,005		
9	7	High pressure mercury lamp	1,007		
10	8	High pressure sodium lamp	1,009		
11	9	Metal halide lamp (3-additive)	1,014		
12	10	Metal halide lamp (rare-earth)	1,009		
13	11	Flourescent display (Material: ZnO:Zn)	1,022		
14	12	Color CRT -red	0,995		
15	13	Color CRT -green	1,018		
16	14	Color CRT -blue	1,123		
17	15	Color CRT -white	1,023		
18	16	CIE Standard Illuminant A + Y-44	1,000		
19	17	CIE Standard Illuminant A + O-54	0,987		
20	18	CIE Standard Illuminant A + R-64	0,856		
21	19				
22	20				
23	21				
24	22				
25	23				
26	24				

You can specify up to 50 CCF factors! (0 – 49)

Only columns C & D can be edited! Column C is a name for the factor whilst column D is the value!

Number of CCF factors is calculated automatically!

Please don't enter names longer than the field as you might not be able to properly read such long name in the drop down list of "Tools" sheet!

## Appendix

### ***Colorimetric calculations:***

#### **1931 CIE Chromaticity System (Yxy)**

$$Y = Y \quad x = \frac{X}{X+Y+Z} \quad y = \frac{Y}{X+Y+Z}$$

#### **1960 CIE Uniform Color Space System (uv)**

$$u = \frac{4X}{(X+15Y+3Z)} \quad v = \frac{6Y}{(X+15Y+3Z)}$$

$$u = \frac{4x}{(-2x+12y+3)} \quad v = \frac{6y}{(-2x+12y+3)}$$

$$x = \frac{1.5u}{(u-4v+2)} \quad y = \frac{v}{(u-4v+2)}$$

#### **1976 CIE Uniform Color Space System (u'v')**

$$u' = \frac{4X}{(X+15Y+3Z)} \quad v' = \frac{9Y}{(X+15Y+3Z)}$$

$$u' = \frac{4x}{(-2x+12y+3)} \quad v' = \frac{9y}{(-2x+12y+3)}$$

$$x = \frac{6.75u'}{(4.5u'-12v'+9)} \quad y = \frac{3v'}{(4.5u'-12v'+9)}$$